



I/O Device Guide

Version 2023.3
2024-05-16

I/O Device Guide

InterSystems IRIS Data Platform Version 2023.3 2024-05-16

Copyright © 2024 InterSystems Corporation

All rights reserved.

InterSystems®, HealthShare Care Community®, HealthShare Unified Care Record®, IntegratedML®, InterSystems Caché®, InterSystems Ensemble®, InterSystems HealthShare®, InterSystems IRIS®, and TrakCare are registered trademarks of InterSystems Corporation. HealthShare® CMS Solution Pack™ HealthShare® Health Connect Cloud™, InterSystems IRIS for Health™, InterSystems Supply Chain Orchestrator™, and InterSystems TotalView™ For Asset Management are trademarks of InterSystems Corporation. TrakCare is a registered trademark in Australia and the European Union.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Memorial Drive, Cambridge, MA 02142, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700

Tel: +44 (0) 844 854 2917

Email: support@InterSystems.com

Table of Contents

1 Introduction to I/O	1
1.1 Introduction	1
1.2 Overview of I/O Commands	1
1.3 OPEN Command	2
1.3.1 Syntax	2
1.3.2 Examples of OPEN on Windows systems	3
1.3.3 Example of OPEN on UNIX® Systems	3
1.4 USE Command	3
1.4.1 Syntax	3
1.4.2 Examples of USE on Windows	4
1.4.3 Examples of USE on UNIX®	4
1.5 READ Command	4
1.5.1 Syntax	4
1.6 WRITE Command	4
1.6.1 Syntax	5
1.6.2 WRITE /mnemonic	5
1.7 CLOSE Command	5
1.7.1 Syntax	5
2 Principal Device, Current Device, and Null Device	7
2.1 One Process Owns a Device	7
2.2 Each Process has a Principal Device	7
2.3 InterSystems IRIS Directs I/O Commands to the Current Device	7
2.4 When Your Principal Device Becomes Your Current Device	8
2.5 Explicitly Using the Principal Device	8
2.6 Options for Working with the Principal Device	8
2.7 The Null Device	9
3 Specifying Devices in I/O Commands	11
3.1 Specifying Terminals and Printers by Device Name	11
3.1.1 Specifying a Terminal on Windows Systems	11
3.1.2 Specifying Terminals and Printers on UNIX®	12
3.2 Specifying Devices by InterSystems IRIS ID	12
3.2.1 Examples	12
3.3 Specifying Files on Disk	12
3.3.1 UNIX Examples	13
4 Local Interprocess Communication (Pipes)	15
4.1 Introduction	15
4.2 Opening Pipes to InterSystems IRIS Utilities	15
4.3 Pipes and Command Pipes	15
4.3.1 Standard Pipe OPEN	15
4.3.2 Command Pipe OPEN	16
4.4 OPEN Command for Interprocess Communication	16
4.4.1 OPEN Arguments	16
4.4.2 OPEN Command Pipe Examples	17
4.4.3 OPEN Errors	18
4.4.4 OPEN and USE Command Keywords	19
4.4.5 OPEN-only Keywords	19

4.5 READ Command for Interprocess Communication	20
4.5.1 Syntax	20
4.6 CPIPE Exit Codes	21
4.7 CLOSE Command for Interprocess Communication	21
4.8 Using Named Pipes to Communicate with Visual Basic	22
4.8.1 OPEN Command Keywords	22
4.9 See Also	23
5 Communication Between InterSystems IRIS Processes	25
5.1 Introduction	25
5.2 Specifying Memory Buffers for Interjob Communication Devices	26
5.2.1 Disabling Interjob Communication Buffers	26
5.3 Interjob Communication Device Numbers	26
5.4 I/O Commands for IJC Devices	27
5.4.1 OPEN Command	27
5.5 See Also	28
6 TCP Client/Server Communication	29
6.1 Introduction	29
6.2 OPEN Command for TCP Devices	30
6.2.1 Using the OPEN Command	30
6.2.2 Server-Side OPEN Command	35
6.2.3 Client-Side OPEN Command	36
6.2.4 OPEN and USE Command Keywords for TCP Devices	37
6.2.5 OPEN-Only Command Keywords for TCP Devices	42
6.3 Current TCP Device	44
6.4 USE Command for TCP Devices	44
6.5 READ Command for TCP Devices	45
6.5.1 READ Modifies \$ZA and \$ZB	46
6.6 WRITE Command for TCP Devices	46
6.6.1 How WRITE Works	47
6.6.2 WRITE Modifies \$X and \$Y	47
6.6.3 WRITE Command Errors	47
6.6.4 WRITE Control Commands	47
6.7 Closing the Connection	48
6.7.1 Disconnect with CLOSE Command	48
6.7.2 Automatic Disconnection	48
6.7.3 Effects of Disconnection	48
6.8 See Also	49
7 TCP Advanced Topics	51
7.1 Connection Management	51
7.1.1 Job Command with TCP Devices	51
7.2 Concatenation of Records	53
7.3 Multiplexing InterSystems IRIS TCP Devices	53
7.4 See Also	54
8 UDP Client/Server Communication	55
8.1 Introduction	55
8.2 Establishing a UDP Socket	55
8.3 The Host Address	56
8.4 IPv4 and IPv6	56
8.5 See Also	57

9 Terminal I/O	59
9.1 Overview	59
9.1.1 Your Login Terminal or Console is Your Principal Device	59
9.2 Special Variables Show I/O Conditions	60
9.2.1 \$X and \$Y and Cursor Position	60
9.2.2 \$TEST Shows Timed Operation Results	62
9.2.3 \$ZA Shows READ Status	62
9.2.4 \$ZB Shows What Ended a READ	62
9.3 OPEN and USE Commands	63
9.3.1 OPEN Command	63
9.3.2 USE Command	64
9.3.3 Positional Parameters for OPEN and USE Commands	65
9.3.4 Keyword Parameters for OPEN and USE Commands	67
9.3.5 Testing the Success of OPEN Commands	70
9.3.6 Letter Code Protocols for OPEN and USE	70
9.3.7 Protocol Terminator Characters	73
9.3.8 Explicit Terminator Characters	74
9.3.9 Summary of Protocols and Terminators in Read Operations	75
9.4 READ Command	76
9.4.1 Syntax	76
9.4.2 Examples	76
9.4.3 Read Line Recall	76
9.4.4 Special Protocol Characters Affect Terminal I/O	77
9.4.5 How the READ Command Processes Input	78
9.5 WRITE Command	79
9.5.1 Syntax	79
9.5.2 Examples	80
9.6 CLOSE Command	81
9.6.1 Syntax	81
9.7 Predefined Mnemonic Spaces for Terminals	81
9.7.1 Mnemonic Space for X3.64	81
9.7.2 Mnemonic Space for DTM PC Console	84
9.7.3 DTM Examples	84
9.8 PRINT and ZPRINT Commands	86
9.8.1 Syntax	86
9.9 Programming Your Terminal	87
9.9.1 Using InterSystems IRIS to Program Formatted CRT Screens	87
9.9.2 Programming Escape Sequences	88
9.9.3 Example	89
9.9.4 InterSystems IRIS Supports Full or Half Duplex and Echo	89
9.9.5 InterSystems IRIS Supports Intercomputer Links and Special Devices	90
10 File I/O	91
10.1 Introduction	91
10.2 Specifying a File	92
10.2.1 File Pathname Tools	93
10.2.2 Tilde (~) Expansion	93
10.3 OPEN Command	94
10.3.1 OPEN Syntax	94
10.3.2 OPEN Mode Parameters	95
10.3.3 OPEN Argument Keywords	99

10.3.4 OPEN Mode Locking	99
10.3.5 Examples	100
10.4 USE Command	101
10.4.1 Syntax	101
10.4.2 USE-Only Command Keywords	101
10.5 READ Command	102
10.5.1 Syntax	102
10.5.2 Example	102
10.6 WRITE Command	103
10.6.1 Syntax	103
10.7 CLOSE Command	103
10.7.1 Syntax	103
10.7.2 CLOSE-Only Command Keywords	103
11 Spool Device	105
11.1 Introduction	105
11.2 Opening and Using the Spool Device	105
11.2.1 OPEN and USE Commands for Spooling Device	106
11.3 Spooling and Special Variables	107
11.4 Closing the Spool Device	108
11.4.1 Changing Namespaces	108
11.4.2 Abort Job Processing	108
11.5 Viewing the ^SPOOL Global	108
11.6 Opening the Spooler Using the %IS Utility	109
11.7 Managing Spooled Documents Using %SPOOL	109
11.7.1 Printing with %SPOOL	110
11.7.2 Listing Spooled Documents	111
11.7.3 Deleting Spooled Documents	112
12 Printers	113
12.1 Overview of Printers	113
12.2 Specifying a Printer	113
12.2.1 Opening a Printer	114
12.2.2 Specifying a Printer on Windows	114
12.2.3 Specifying a Printer on UNIX®	115
12.3 Directing Output to a Printer	115
12.3.1 %IS Printer Set-Up Variable	116
12.4 Printer as Alternate Device	116
13 Controlling Devices with Mnemonic Spaces	117
13.1 Predefined Mnemonic Spaces	117
13.2 Setting Up Default Mnemonic Spaces	117
13.3 Creating a Mnemonic Space	118
13.4 Select a Mnemonic Space	118
14 Managing Devices and Mnemonic Spaces	119
14.1 Device Management Utilities	119
14.2 Default Devices	120
14.2.1 Devices	120
14.2.2 Device Subtypes	120
14.3 Identifying Devices	120
14.3.1 Device Mnemonics	120
14.3.2 Device IDs	121

14.3.3 Device Alias	121
14.3.4 Default Device IDs and Mnemonics	121
14.3.5 Device Types	122
14.4 Defining Devices	122
14.5 Accessing Devices	122
14.5.1 Allowing Users to Select Devices with the ^%IS Utility	123
14.5.2 Accessing Devices with the OPEN Command	123
14.5.3 Interpretation Levels for Devices	123
14.6 Defining Default Mnemonic Spaces	124
14.6.1 Predefined Mnemonic Spaces	124
15 Using ^%IS	125
15.1 How ^%IS Works	125
15.1.1 Device Prompt	125
15.1.2 Additional Questions	125
15.1.3 Examples	126
15.1.4 ^%IS Sets the Variable IO and Returns Values of Other Variables	126
15.1.5 OPEN Parameters	126
15.1.6 Issue a USE Command	126
15.1.7 Issue a CLOSE Command	127
15.2 ^%IS Mnemonics	127
15.2.1 Device Mnemonics	127
15.2.2 Default Mnemonics	127
15.2.3 Alternate Devices	127
15.2.4 CURRENT^%IS Entry Point	127
15.2.5 Example	128
15.2.6 IN^%IS Entry Point	128
15.2.7 OUT^%IS Entry Point	128
15.2.8 Spooling	128
15.2.9 Further Features of ^%IS	129
15.3 Structure of ^%IS Global	129
15.3.1 Contents of Node 0	130
15.3.2 Contents of Node 1	130
16 Device Special Variables	131

List of Figures

Figure 7–1: Client/Server Connections in the Non-Concurrent and Concurrent Modes.	52
Figure 9–1: READ Command Processing Normal (Non-Image) Mode	78
Figure 9–2: READ Command Processing Image Mode	79

List of Tables

Table 2–1: Null Device Arguments	9
Table 3–1: Specifying a Device in an I/O Command	11
Table 3–2: InterSystems IRIS Device Numbers and Devices	12
Table 5–1: IJC Device Numbers	26
Table 9–1: Effects of Echoing Characters	60
Table 9–2: \$ZA Read Status Values	62
Table 9–3: OPEN and USE Keyword Parameters for Terminal Devices	67
Table 9–4: Letter Code Protocols for OPEN and USE	71
Table 9–5: Terminator Strings: Examples	75
Table 9–6: READ Command Arguments: Examples	76
Table 9–7: Output Control Characters	77
Table 9–8: Input Control Characters	77
Table 9–9: Control Mnemonics for %X364 Mnemonic Space	81
Table 9–10: Control Mnemonics for DTM PC Console	85
Table 9–11: Features Enabled By CURRENT^%IS	88
Table 10–1: OPEN Mode Parameters	95
Table 10–2: OPEN Keyword Arguments for Sequential Files	99
Table 10–3: Windows OPEN Mode Interactions	99
Table 10–4: UNIX® OPEN Mode Interactions	100
Table 10–5: USE-Only Command Keywords for Sequential Files	101
Table 10–6: CLOSE-Only Command Keywords for Sequential Files	104
Table 11–1: OPEN Positional Parameters for Spooling	106
Table 12–1: Additional OPEN Keyword Parameters for Windows Printers	115
Table 12–2: Variables Set by %IS	116
Table 13–1: Predefined Mnemonic Spaces	117
Table 14–1: InterSystems IRIS Device Utilities	119
Table 14–2: Default Device Numbers and Mnemonics	121
Table 14–3: InterSystems IRIS Default Device Numbers	121
Table 14–4: Predefined Mnemonic Spaces	123
Table 14–5: Device Utilities	123
Table 15–1: ^%IS Device Variable Values	126
Table 15–2: CURRENT Return Values	128
Table 15–3: Spool Variables You Can Pass to ^%IS	129
Table 16–1: Device Special Variables	131

1

Introduction to I/O

This page describes — at a high level — how to work with I/O devices within InterSystems IRIS® data platform applications and at the InterSystems IRIS prompt.

1.1 Introduction

InterSystems IRIS® data platform provides support for many different kinds of devices, both logical and physical. The supported logical devices include:

- The [principal device](#)
- [Files](#)
- [Pipes](#)
- [TCP connections](#)
- [Interjob communication \(IJC\) devices](#) to communicate between InterSystems IRIS processes
- [The InterSystems Spooler](#)

The supported physical devices include:

- [Terminals](#)
- [Printers](#)

1.2 Overview of I/O Commands

The I/O commands allow you to own, use, read from, write to, and close devices. To direct I/O operations to a device, first issue the following commands:

- Issue an **OPEN** command to establish ownership, unless the device is your principal device.
- Issue a **USE** command to make the device the current device.
- Subsequent **READ** and **WRITE** commands read from and write to that device.
- A **CLOSE** command releases ownership of the device so that other processes can use the device.

The following general syntax applies to I/O commands that support I/O command keywords in ObjectScript:

```
OPEN device:paramlist:timeout:"mnespace"  
USE device:paramlist:"mnespace"  
CLOSE device:paramlist
```

where *paramlist* is either a single parameter, or a list of parameters enclosed in parentheses and separated by colons:

```
parameter (parameter:parameter[:...])
```

A *parameter* can either be a positional parameter or a keyword parameter. A keyword parameter has the following syntax:

```
/keyword[=value]
```

The leading slash distinguishes a keyword parameter from a positional parameter value. The meaning of a positional parameter value is derived from its position in the colon-delimited list. The meaning of a keyword parameter value is derived from the specified keyword.

Note that both positional and keyword parameters can be specified in the same *paramlist*. For example, the following example mixes positional and keyword parameters to open a new file named `test.dat` in `write/sequential` mode with JIS I/O translation:

ObjectScript

```
OPEN "test.dat":("NWS":/IOTABLE="JIS")
```

1.3 OPEN Command

OPEN establishes ownership of, and opens an I/O channel to, the device specified. This ownership persists until you issue a **CLOSE** command, your process terminates, or some physical operation closes the device. For physical I/O devices or for interprocess communications (such as TCP connections), this ownership prevents all other processes from accessing the device. For logical I/O devices (such as sequential files), this ownership may allow other processes some form of shared access to the file. The handling of multiple processes that open the same sequential file is highly platform-dependent. Use of the **LOCK** command to restrict access to sequential files is strongly advised.

1.3.1 Syntax

```
OPEN device::{(parameters)}::{timeout}::{:"mnespace"}}}
```

device

The desired device name, ID number, or mnemonic. The maximum length of *device* is 256 characters.

parameters

Optional — One or more parameters specifying additional information necessary for some devices. This parameter list is enclosed in parentheses, and the parameters in the list are separated by colons. The available parameters are different for [pipes \(interprocess communications\)](#), [files](#), and [Terminal I/O](#).

timeout

Optional — The number of seconds to wait for the request to succeed. The preceding colon is required. *timeout* must be specified as an integer value or expression. If *timeout* is set to zero (0), **OPEN** will make a single attempt to open the file. If the attempt fails, the **OPEN** immediately fails. If the attempt succeeds it successfully opens the file. If *timeout* is not set, InterSystems IRIS will continue trying to open the device until the **OPEN** is successful or the process is terminated manually.

mnespace

Optional — The name of the [mnemonic space](#) that contains the control mnemonics to use with this device, specified as a quoted string. You can use these control mnemonics with the **WRITE /mnemonic** command when directing I/O to this device.

For further details, refer to the [OPEN](#) command in the *ObjectScript Reference*.

1.3.2 Examples of OPEN on Windows systems

This command opens outbound Telnet connections from a Windows system to a terminal server:

ObjectScript

```
OPEN "|TNT|node:port"
```

where *node* is the node name and *port* is the IP port on the server.

This command opens an I/O channel to an existing Windows file:

ObjectScript

```
OPEN "c:\abc\test.out": "WS"
```

1.3.3 Example of OPEN on UNIX® Systems

This command opens an I/O channel to the UNIX® terminal device /dev/tty06:

ObjectScript

```
OPEN "/dev/tty06/"
```

1.4 USE Command

This command makes the specified device the current device, and sets the special variable *\$IO* to that device. To **USE** a device other than your principal device, you must first issue an **OPEN** command for it; otherwise, you will receive a <NOTOPEN> error. Arguments have the same meaning as in the **OPEN** command.

1.4.1 Syntax

```
USE device:(args): "mnespace"
```

device

The desired device name, ID number, or alias. The maximum length of *device* is 256 characters.

args

Optional — Additional information necessary for some devices. The available parameters are different for [pipes \(interprocess communications\)](#), [files](#), and [Terminal I/O](#).

mnespace

Optional — Name of the InterSystems IRIS routine containing the definition of the control [mnemonics](#) you can use with the **WRITE** /mnemonic command when directing I/O to this device.

For further details, refer to the [USE](#) command in the *ObjectScript Reference*.

1.4.2 Examples of USE on Windows

This Windows example shows the commands you would use to connect via TCP to a time-of-day server on remote host `larry`. It uses the service name `daytime`, which the local system resolves to a port number. The **USE** command replaces the **OPEN** C mode with PSTE mode and turns off any user terminators:

ObjectScript

```
OPEN "|TCP|4":("larry":"daytime":"C")
USE "|TCP|4":("PSTE")
```

1.4.3 Examples of USE on UNIX®

This UNIX® example shows the commands you would use to open an I/O channel to device `/dev/tty06` and establish it as your current device with the option of using **WRITE** /mnemonic with the X364 terminal mnemonics.

ObjectScript

```
OPEN "/dev/tty06"
USE "/dev/tty06":("^%x364")
```

1.5 READ Command

This command reads data from the current device. For some devices, arguments that begin with asterisks return ASCII numeric information; for others, they indicate control functions.

1.5.1 Syntax

```
READ variable:timeout
```

For further details, refer to the [READ](#) command in the *ObjectScript Reference*.

1.6 WRITE Command

This command writes data to the current device. For some devices, arguments that begin with asterisks let you write ASCII characters using their ASCII numeric values; for others, they indicate control functions. For some devices, arguments that begin with the `#` character indicate the number of times to write that character.

1.6.1 Syntax

```
WRITE variable
```

For further details, refer to the [WRITE](#) command in the *ObjectScript Reference*.

1.6.2 WRITE /mnemonic

WRITE /mnemonic syntax allows you to control a device with [mnemonics](#) which are defined in InterSystems IRIS code in a mnemonic space. The mnemonic space is an InterSystems IRIS routine that must be made active in an **OPEN** or **USE** command, or configured as a default for the device using the Management Portal. To learn how to define and activate mnemonic spaces, see [Defining Default Mnemonic Spaces](#).

To move the cursor to column 1, line 2 on a terminal screen using the predefined `^%X364` mnemonic space, issue the command:

ObjectScript

```
WRITE /CUP(1,2)
```

1.7 CLOSE Command

The **CLOSE** command releases ownership of the specified device. **CLOSE** reverses the effect of the **OPEN** command.

1.7.1 Syntax

```
CLOSE device[:params]
```

device

The desired device name, ID number, or mnemonic.

params

The parameter `K` closes the device at the InterSystems IRIS level without closing it at the operating system level.

The `K` parameter has no effect on Windows systems. The file is closed at the operating system level.

If you issue a **CLOSE** command for your principal device, the principal device remains assigned to your process until you log off.

Several other conditions can affect the behavior of **CLOSE**:

- If output to a device is stopped for some reason, InterSystems IRIS may be unable to finish output to that device, in which case you cannot close it, and may not be able to halt. For example, if a terminal sends a **Ctrl-S** to the operating system to tell it to stop output to the terminal, you must resume output to the terminal by pressing **Ctrl-Q**.
- If you close the current device, **CLOSE** changes the value of the system variable `$IO` to that of the principal device. The **CLOSE** command releases ownership of the current device only after all output to that device is complete.
- When a process halts, the system automatically closes all devices the process opened while in InterSystems IRIS.

If output to the device is stopped for some reason, InterSystems IRIS may be unable to finish output to that device, in which case you may not be able to close it or be able to halt.

For further details, refer to the [CLOSE](#) command in the *ObjectScript Reference*.

2

Principal Device, Current Device, and Null Device

2.1 One Process Owns a Device

Only one process can own a device at a time, except sequential files.

In other words, after a process successfully issues an **OPEN** command for a device, no other process can open that device until the first process releases it. A process releases the device in any of the following ways:

- By explicitly issuing a **CLOSE** command.
- By halting.

2.2 Each Process has a Principal Device

Each InterSystems IRIS process has one principal input device and one principal output device. By default, these are the same device. When you log in at a terminal and activate InterSystems IRIS, that terminal becomes your principal device. Because InterSystems IRIS implicitly issues **OPEN** and **USE** commands for that terminal, you can issue **READ** and **WRITE** commands to it immediately. The InterSystems IRIS principal device is the one that your operating system has assigned as your principal input device. The **\$PRINCIPAL** special variable contains the device ID of the principal device.

2.3 InterSystems IRIS Directs I/O Commands to the Current Device

InterSystems IRIS directs input and output operations, including **READ**, **WRITE**, **PRINT**, and **ZLOAD** commands, to your current device. The **\$IO** special variable contains the device ID of your current device. When you log in to InterSystems IRIS at a terminal, **\$IO** initially contains your terminal's device name. In other words, your principal device and your current device are the same immediately after you log in. After you issue a **USE** command, your current device (the one contained in **\$IO**) is normally the one named in the last **USE** command you executed.

Although you may issue **OPEN** and **USE** for a device other than your principal device in programmer mode, each time InterSystems IRIS returns to the > prompt, it implicitly issues **USE 0**. To continue using a device other than 0, you must issue a **USE** command in each line you enter at the > prompt.

2.4 When Your Principal Device Becomes Your Current Device

Your principal device automatically becomes your current device when you do any of the following:

- Sign on for the first time.
- Issue a **USE 0** or **USE \$principal** command.
- Issue a call to the **ChangePrincipal()** method of the `%Library.Device` class.
- Cause an error when an error trap is not set.
- Close the current device.
- Return to programmer mode.
- Exit InterSystems IRIS by issuing a **HALT** command.

2.5 Explicitly Using the Principal Device

USE 0 or **USE \$principal** implicitly issues an **OPEN** command to the principal device for the process. If another process owns the device, this process hangs on the implicit **OPEN** as it does when it encounters any **OPEN**.

Issuing a **USE** command for any other device that the process does not own (due to a previous **OPEN** command) produces a <NOTOPEN> error.

An **OPEN** command with no timeout returns control to the process only when the process acquires the device. You can interrupt the open command by a keyboard interrupt command like **Ctrl-C**. An **OPEN** that cannot succeed because of a protection problem or an invalid device name hangs forever. When you specify a timeout in the **OPEN** command, the **OPEN** returns control to your process when the timeout expires.

2.6 Options for Working with the Principal Device

Depending on the nature of the principal device, you can specify additional device-specific arguments, which are different for [pipes \(interprocess communications\)](#), [files](#), and [Terminal I/O](#). For example, you can open the principal device with the TLS connection:

```
USE $principal:(::/TLS=ConfigName)
```

Where *ConfigName* is the name of a TLS configuration defined in the same instance.

2.7 The Null Device

If your application generates extraneous output which you do not want to appear on your screen, you can direct that output to the null device. You specify the null device by issuing an InterSystems IRIS **OPEN** command with the appropriate argument (see table). InterSystems IRIS treats it as a dummy device.

Table 2-1: Null Device Arguments

Platform	Null Device Argument
UNIX®	/dev/null/
Windows	//./nul

Subsequent **READ** commands immediately return an empty string. Subsequent **WRITE** commands immediately return success. No actual data is read or written. The NULL device bypasses UNIX® open, write, and read system calls entirely.

Note: If you open the NULL device other than from within InterSystems IRIS (for example, by redirecting InterSystems IRIS output to /dev/null from the UNIX® shell), the UNIX® system calls do occur as they would for any other device.

Note: When one process starts another with the **JOB** command, the default principal input and output device of the jobbed process is the null device.

3

Specifying Devices in I/O Commands

When you use the I/O commands **OPEN**, **USE** and **CLOSE** to process I/O on any device other than the one on which you are working, you must specify an I/O device. You can specify devices in one of three ways, depending on device type, as shown in the table below.

Table 3–1: Specifying a Device in an I/O Command

Type of Specification	Use for these Devices
InterSystems IRIS Device Name	Terminals and Printers
InterSystems IRIS Device ID or Device Alias	All devices except sequential files
File Name	Sequential Files

Note that Windows and UNIX® handle printer I/O differently. For details, refer see [Printers](#).

3.1 Specifying Terminals and Printers by Device Name

If your I/O operations are to terminal (or a printer on some platforms), you can use the device name applied by the operating system (UNIX® or Windows) to specify the device. The form is as follows:

```
OPEN "device"  
USE "device"  
CLOSE "device"
```

Where *device* is the operating system name of the device, enclosed in quotes. The maximum length of *device* is 256 characters.

3.1.1 Specifying a Terminal on Windows Systems

To open an I/O device connected to a serial communications port, specify an **OPEN** command with the following syntax:

```
OPEN "comn:"
```

Where *n* represents the number of the port to which the device is attached.

ObjectScript

```
OPEN "com1:"
```

3.1.2 Specifying Terminals and Printers on UNIX®

To open an I/O device on a terminal that has the UNIX® device name `/dev/tty06`, enter the following command

ObjectScript

```
OPEN "/dev/tty06"
```

On UNIX® systems, a printer is identified by the name on the **OPEN** command and is handled as a “character special” file on a tty device. Thus the **OPEN** and **USE** command arguments supported are the same as those for terminal I/O, *not* sequential file I/O. On Windows systems, printer I/O *is* handled like sequential file I/O.

3.2 Specifying Devices by InterSystems IRIS ID

For compatibility with other InterSystems products and for convenience, you can refer to devices by device numbers (which are stored in the device table). The system manager can link these numbers to devices using the Management Portal. Select **System Administration, Configuration, Device Settings, Devices** to create a new device or edit an existing device.

The system manager can also cause a translation from one number to another. Thus, you can issue an `OPEN 47` and InterSystems IRIS will translate it to `OPEN 49`.

The following table shows the device numbers.

Table 3–2: InterSystems IRIS Device Numbers and Devices

Device Numbers	Devices
0	Principal device (the device on which you logged in).
2	InterSystems IRIS spooler. UNIX®: the mnemonic SPOOL applies to this device.
3	An invalid device number. Attempting to open it returns a <NOTOPEN> error without waiting for <i>timeout</i> expiration.
63	View buffer.
20-46, 200-223	Routine interlock devices.
224-255	Interjob communication devices.

3.2.1 Examples

To open the spooler, you issue the command:

ObjectScript

```
OPEN 2
```

3.3 Specifying Files on Disk

You can open a disk file using the operating system file specification enclosed in double quotes.

A Windows file specification has the following format:

```
device:\directory\file.type
```

A UNIX® file specification has the following format:

```
/directory/name
```

For further details, see [Specifying a File](#).

3.3.1 UNIX Examples

If your current default directory on a UNIX® or Windows system is `/usr/user`, you can open a file named `pat_rec.dat` stored in your current default directory by specifying:

ObjectScript

```
OPEN "pat_rec.dat"
```

The system opens the file automatically. For a new file, include the parameter string `WN` to avoid a hang.

To open a file with the same name, `pat_rec.dat`, stored in another directory, you must also specify the directory, as follows:

ObjectScript

```
OPEN "/usr/elsewhere/pat_rec.dat"
```


4

Local Interprocess Communication (Pipes)

This page describes how to set up communication with processes outside of InterSystems IRIS® data platform via pipes.

4.1 Introduction

You can communicate between your InterSystems IRIS processes and external UNIX® or Windows processes through a pipe, just as at the UNIX® or Windows operating system level. You can send output to or receive input from the pipe. The pipe is one-way; you cannot read from and write to the same program at the same time.

When you open a pipe to another program for output, you can write to it as if it were a sequential file. The program then uses what you have written as its input stream. This capability is especially helpful when you want InterSystems IRIS processes to share resources with external processes.

4.2 Opening Pipes to InterSystems IRIS Utilities

You can open a pipe to an InterSystems IRIS utility as well as to UNIX® or Windows processes. Before you can use a pipe for utility I/O, your system manager must define the pipe device on your InterSystems IRIS system.

After the system manager defines the pipe device, when you run a utility (such as `^%RD`), you answer the `Device:` prompt with the mnemonic the system manager defined. Your output goes automatically to that device.

4.3 Pipes and Command Pipes

InterSystems IRIS supports both standard pipes and command pipes (CPIPE). Standard pipes are used for relative short command strings, in which the command name and its arguments are less than 256 characters. Command pipes are used when the command string is 256 characters or more in length. In both cases, pipes can only be used on UNIX® and Windows systems.

4.3.1 Standard Pipe OPEN

The following is the **OPEN** command syntax for standard pipes:

```
OPEN program:(parameters):timeout
```

Because *program* is the first argument (the device argument), it must follow the **OPEN** command device name limitation of 256 characters.

If an **OPEN** command is issued for a standard pipe that is already open, the second **OPEN** is ignored. No error is issued.

4.3.2 Command Pipe OPEN

The following is the **OPEN** command syntax for command pipes:

```
OPEN cpipename:program:timeout
OPEN cpipename:(program:parameters::closetimeout):timeout
```

The *cpipename* argument can take the value "`|CPIPE|`" if there is only command pipe open concurrently. To open multiple concurrent pipes, specify "`|CPIPE|xxxxxx`", where *xxxxxx* represents a user-specified unique identifier. This *cpipename* argument is the argument specified for subsequent **USE** and **CLOSE** commands.

Because *program* is the second argument, it is not limited to 256 characters. The maximum length of *program* is platform dependent.

If an **OPEN** command is issued for a command pipe that is already open, the second **OPEN** is ignored. No error is issued.

4.4 OPEN Command for Interprocess Communication

The **OPEN** command allows your program to communicate with processes external to InterSystems IRIS.

4.4.1 OPEN Arguments

cpipename

Command Pipes Only — either "`|CPIPE|`" or "`|CPIPE|xxxxxx`", where *xxxxxx* represents a user-specified unique identifier.

program

A command pipe can execute a *program* with a command shell, or without a command shell (directly). Executing without a command shell is preferred in most situations. A standard pipe executes a *program* with a command shell.

Command Pipes Only — To execute without a command shell, specify `/COMMAND=program`. If *program* has arguments, you must specify them using the `/ARGS` keyword. If you specify either the `/COMMAND` or `/ARGS` keyword, the *program* is executed without a command shell: `(/COMMAND=program)`, `(/COMMAND=program:/ARGS=arg1)` and `(program:/ARGS=arg1)` are all valid syntax. `/ARGS` can take a single argument, a comma-separated list of arguments, or an array. For example, `(/COMMAND=program:/ARGS=arg1, arg2)`. You can specify a variable number of arguments using an array:

ObjectScript

```
SET array(1)=arg1, array(2)=arg2, array=2
OPEN device:(/COMMAND=cmd:/ARGS=array...)
```

To execute using a command shell, specify *program*, omitting both the `/COMMAND` and `/ARGS` keywords.

The *program* string contains the [full pathname](#) of a program installed on your system. It contains the command name and its arguments (if any) to be executed on the host system. For a standard pipe, limited to <256 characters. For command pipe, the maximum length is platform dependent, but substantially more than 256 characters.

parameters

Read. For a standard pipe specify Q or QR to open a queue or pipe to accept input from another process. For a command pipe: because a command pipe is unambiguously a pipe, the Q letter code is not required; specify R.

Write. For a standard pipe specify QW to open a queue to send input to another process. For a command pipe: because a command pipe is unambiguously a pipe, the Q letter code is not required; specify w.

Read and Write. For a standard pipe that can be either a read or write pipe specify QRW to open a queue or pipe to accept input from and send input to another process. For a command pipe: because a command pipe is unambiguously a pipe, the Q letter code is not required; specify RW.

You can specify these and other parameters using the */keyword* parameters, separated by colons. For example, `OPEN " |CPIPE | " : (cmd : /READ : /IOTABLE="UTF8 ")`. The following optional keyword parameters are commonly used with pipes:

- *K/name/* (or *Knum*) to enable I/O translation, if translation has been enabled system-wide. You identify the previously defined table on which the translation is based by specifying the table's name. The + and - options for turning protocols on and off are not available with the K protocol.
- *Y/name/* (or *Ynum*) to tell the system to use the named \$X/\$Y Action Table. You identify the previously defined \$X/\$Y Action Table on which translation is based by specifying the table's name. \$X/\$Y action is always enabled. If Y is not specified and a system default \$X/\$Y is not defined, a built in \$X/\$Y action table is used. The + and - options for turning protocols on and off are not available with the Y protocol.

You can specify the S (stream), F (fixed length), or U (undefined length) mode parameters with the above parameters. You *cannot* specify the V (variable length) mode parameter.

For a complete list of letter code and keyword parameters, refer to [OPEN Mode Parameters](#).

closetimeout

Optional — UNIX® only: You can specify the number of seconds the **CLOSE** command will wait for the command process to exit when closing a piped command device. The default is 30 seconds. You can override this *closetimeout* by specifying an "I" (immediate) argument on the [CLOSE command for interprocess communication](#).

timeout

Optional — A positive integer whose value in seconds is the longest time InterSystems IRIS waits for an **OPEN** to successfully finish. If InterSystems IRIS is able to open interprocess communication before the timeout expires, it sets **\$TEST** to 1. If InterSystems IRIS is not able to open interprocess communication before the timeout expires, it sets **\$TEST** to 0. If you omit the timeout or specify 0, the **OPEN** returns control to the process immediately.

4.4.2 OPEN Command Pipe Examples

The following are valid command pipe **OPEN** statements. Each example specifies a timeout of 10 seconds:

ObjectScript

```
OPEN " |CPIPE | 1 " : "/nethome/myprog" : 10 // using shell, no args
OPEN " |CPIPE | 1 " : ( " : "/nethome/myprog" : /WRITE ) : 10 // using shell, no args, WRITE

OPEN " |CPIPE | 2 " : /COMMAND="/nethome/myprog" : 10 // no shell, no args
OPEN " |CPIPE | 3 " : ( " " : /COMMAND="/nethome/myprog" ) : 10 // no shell, no args
OPEN " |CPIPE | 4 " : ( /COMMAND="/nethome/myprog" : /ARGS=arg1 ) : 10 // no shell, 1 arg
OPEN " |CPIPE | 5 " : ( " /nethome/myprog" : /ARGS=arg1 ) : 10 // no shell, 1 arg
OPEN " |CPIPE | 6 " : ( " /nethome/myprog" : /ARGS=arg1 : /WRITE ) : 10 // no shell, 1 arg, WRITE
OPEN " |CPIPE | 7 " : ( /COMMAND="/nethome/myprog" : /ARGS=arg1, arg2 ) : 10 // no shell, 2 args
OPEN " |CPIPE | 8 " : ( /COMMAND="/nethome/myprog" : /ARGS=args... : /WRITE ) : 10 // no shell, args array, WRITE
```

On a Windows system, an argument can include a blank space or a double quote (") character. In these cases, the argument can be quoted, and a literal double quote character can be escaped by doubling it:

ObjectScript

```
OPEN "|CPIPE|9":("/nethome/myprog":/ARGS="string with blanks"):10
OPEN "|CPIPE|10":("/nethome/myprog":/ARGS="string with literal "" character"):10
```

4.4.3 OPEN Errors

If you issue an **OPEN** command with the **QW** parameter for a non-IPC device, a <WRITE> error occurs when you try to write to this device.

The following UNIX® example opens an output pipe to the **lp** program, whose pathname in this case is **/usr/bin/lp**. Then it sends output from the global **^TEXT** to the printer through this pipe.

ObjectScript

```
print ; Send the first layer of global ^TEXT to the printer.
      SET IO="/usr/bin/lp"
      OPEN IO:"QW" ; Open the pipe to lp
      USE IO WRITE "The first layer of ^TEXT",! ; Print the title
      ;
      ; Print each line, using $ORDER on the global ^TEXT
      USE IO WRITE !,"The End.",#
      CLOSE IO ; close the pipe, spooling the file to lpsched
      QUIT
```

You can alter this example so that the **OPEN** command passes arguments to the **lp** program. For example, to specify that **lp** should send the output to the printer device named **laserjet**, you could replace the **SET** command with the following:

ObjectScript

```
SET IO="/usr/bin/lp -dlaserjet"
```

The following example shows how to read from an external program. Here the process opens an input pipe to the UNIX® program **who**, so that it can read the IDs of all users who are currently logged in to UNIX®.

ObjectScript

```
getids ; read the login IDs of everybody currently on
      SET IO="/usr/bin/who"
      SET $ZTRAP="EOT"
      KILL LOGINS
      OPEN IO:"Q"
      ; note that "R" (the default) is understood
      SET users=0
      FOR I=0:0 {
        USE IO
        READ USER
        SET users=users+1
        SET LOGINS(USER)=" "
      }
      QUIT
EOT   SET $ZTRAP=""
      USE 0
      WRITE !,USERS," is/are currently logged on.",!
      CLOSE IO
      QUIT
```

On a Windows system, when a **CPIPE OPEN program** argument specifies **/COMMAND** or **/ARGS**, the system uses **CreateProcess()** to run the command. If the **CreateProcess()** fails, the **OPEN** will fail with a <NOTOPEN> error. The **GetLastError()** value is available via **\$\$SYSTEM.Process.OSError()**.

On a UNIX® system, when a CPIPE **OPEN** *program* argument specifies `/COMMAND` or `/ARGS`, the system creates a new process which issues an `exec()` to run the command. If the `exec()` fails, the **OPEN** will fail with a `<NOTOPEN>` error. The `exec()` `errno` is available via `$SYSTEM.Process.OSError()`.

4.4.4 OPEN and USE Command Keywords

The following list describes the keywords for controlling interprocess communications pipes with both **OPEN** and **USE** commands.

/IOTABLE[=*name*]

Or:

`/IOT[=name]`

Default: If *name* is not specified, the default I/O translation table for the device is used.

Corresponds to the `K\name\` parameter code, which establishes an I/O translation table for the device.

/TRANSLATE[=*n*]

Or:

`/TRA[=n]`

Default: 1

Associated with the `K` parameter code. `/TRANSLATE` or `/TRANSLATE=n` for nonzero values of *n* enable I/O translation for the device. `/TRANSLATE=n` for a zero value of *n* disables I/O translation for the device.

/XYTABLE[=*name*]

Or:

`/XYT[=name]`

Default: If *name* is not specified, the default `$X/$Y` action table for the device is used.

Corresponds to the `Y\name\` parameter code, which establishes a `$X/$Y` action table for the device.

4.4.5 OPEN-only Keywords

The following list describes the keywords for controlling interprocess communications pipes with only the **OPEN** command.

/ENV=environmentvars

Specifies environment variables to be set in the new process. There are two ways to specify the values:

- Explicitly. For example:

```
/ENV=(name1:value1,name2:value2)
```

- Via a multidimensional array. For example:

```
Set arr(name1)=value1
Set arr(name2)=value2

// then later use the following in the OPEN command:
/ENV=arr...
```

The examples show two environment variables but there can be any number. The explicit list must be enclosed in parentheses.

/IGNOREEOF[=*n*]

Or:

`/IGN[=n]`

Default: 0

Corresponds to the **I** parameter code, which specifies that a **READ** operation should be retried (ignoring any EOF condition) indefinitely or until the specified timeout expires. `/IGNOREEOF` or `/IGNOREEOF=n` for nonzero values of *n* enable the parameter code and `/IGNOREEOF=n` for a zero value of *n* disables the parameter code.

/PARAMS=*str*

Or:

`/PAR=str`

No default.

Corresponds to the parameter codes positional parameter. (It provides a way to specify a parameter code string in a position independent way.)

/QUEUE

Or:

`/QUE`

Default: The device is not recognized as an interprocess communications pipe.

Corresponds to the **Q** parameter code, which specifies that an interprocess communications pipe should be opened. Note that using this command requires Use permission on the `%System_Callout` resource.

/Read

Default: Read is the default if neither `/Read` nor `/Write` is specified.

Corresponds to the **R** parameter code, which specifies that a queue or pipe should be opened to accept data from another process.

/Write

Or:

`/WRI`

Default: Read is the default if neither `/Read` nor `/Write` is specified.

Corresponds to the **W** parameter code, which specifies that a queue or pipe should be opened to send data to another process.

4.5 READ Command for Interprocess Communication

4.5.1 Syntax

`READ:pc readargument,...`

READ reads data from a pipe.

where *readargument* can be:

```
formatting-mode
string
variable:timeout
*variable:timeout
variable#n:timeout
```

Use the *I formatting-mode* parameter with pipes. The *I* parameter lets you issue a timed **READ** for a named pipe without losing any data that can occur in a partial record that follows an <ENDOFFILE> error. When you use this parameter on a **READ**, the **READ** ignores <ENDOFFILE> messages.

The value of the *I formatting-mode* is off by default. If you include this parameter in a **READ** command without a timeout, your process hangs until there is data to process.

4.6 CPIPE Exit Codes

You can retrieve the exit code of a command pipe (CPIPE) process. This exit code must be retrieved before the CPIPE device is closed. It is obtained with the **PipeExitCode** method of the %SYSTEM.Process class. Exit codes are always integer values. If the exit code is not available, the method returns a null string and sets the status argument with an explanation, as shown in the following example:

ObjectScript

```
SET exitcode=$SYSTEM.Process.PipeExitCode(device, .status)
IF exitcode="" {DO $SYSTEM.OBJ.DisplayError(status)}
ELSE {WRITE "CPIPE exit code is ",exitcode }
```

On a UNIX® system, an exit code is available only for non-shell commands; that is, CPIPE devices opened with /COMMAND or /ARGS.

4.7 CLOSE Command for Interprocess Communication

If you create a child process using **OPEN** with a Q (/QUEUE) parameter code, the child process may survive a **CLOSE** operation on the device. Survivability of a queued interprocess communications pipe is platform-dependent. On UNIX® systems the child process always survives the **CLOSE**. On Windows systems the survival of the process depends upon how old the process is. A child process that has just been initiated does not survive a **CLOSE** operation, but once a child process is fully established it survives a **CLOSE**.

On UNIX® systems, you can specify the how long the **CLOSE** command should wait when closing a piped command device. The timeout default is 30 seconds. You can modify this default by specifying the **OPEN** command *closetimeout* positional argument. You can override the default or specified timeout for a **CLOSE** command by specifying the optional “I” positional argument. The “I” argument specifies immediate close (close after 1 second). The **CLOSE** syntax is as follows:

```
CLOSE cpipename:"I"
```

4.8 Using Named Pipes to Communicate with Visual Basic

On Windows, use named pipes in InterSystems IRIS as you would use TCP devices, but use the device name `|NPIPE|nnn` instead of `|TCP|nnn`. The **OPEN** arguments are as follows:

```
OPEN "|NPIPE|3":(server:pipeName)
```

where *server* is the machine name, and *pipeName* is the name of the pipe that it is to be connected to.

To connect to a local pipeName, use `"."` (a quoted period) as a server. To create a pipe (as a server), use `"` (quotes without content) as the server name. The following are all valid *server* names:

ObjectScript

```
OPEN "|NPIPE|3":(".":"localpipe")
OPEN "|NPIPE|3":("mother":"test")
OPEN "|NPIPE|3":("":"info")
```

A server can open a named pipe and immediately issue a write before the client side has opened the same named pipe. The write operation will hang until the client side opens the named pipe. A user can interrupt the hang by issuing a Control-C.

Once open, a pipe acts like an ordinary device. On the server side, clients can be disconnected as in TCP with:

ObjectScript

```
USE "|NPIPE|3": "DISCONNECT"
```

Alternatively:

ObjectScript

```
USE "|NPIPE|3" WRITE *-2
```

4.8.1 OPEN Command Keywords

The following list describes the keywords for controlling named pipes with only the **OPEN** command.

/HOSTNAME=*str*

Or:

```
/HOS=str
```

Default: The default is `"` (empty string) which opens the pipe as a server.

Corresponds to the server positional parameter, which specifies the Windows computer. It is not necessary to specify this keyword when opening the pipe as a server. Use `"."` (a quoted period) to connect to a local pipeName.

/BUFSIZE=*n*

Or:

```
/BU=n
```

Default: 2048

Specifies the size of the named pipe input buffer that holds data received from the pipe but not yet delivered to the application.

/INSTANCES=*n*

Or:

`/INS=n`

Default: 1

Specifies the maximum number of instances allowed for the named pipe. A value greater than 1 allows more than one server to open an instance of the named pipe, so that more than one client at a time can be served.

/OBUFSIZE=*n*

Or:

`/OBU=n`

Default: 2048

Specifies the size of the output buffer used by the operating system. This buffer size is advisory, since the operating system sizes the buffer according to system-imposed constraints.

/PIPENAME=*str*

Or:

`/PIP=str`

No default.

Corresponds to the *pipename* positional parameter which specifies the name of the pipe.

4.9 See Also

- [TCP Client/Server Communication](#)
- [TCP Advanced Topics](#)
- [UDP Client/Server Communication](#)
- [Communication Between InterSystems IRIS Processes](#)

5

Communication Between InterSystems IRIS Processes

This page describes how to set up communication between two or more InterSystems IRIS® data platform processes.

5.1 Introduction

Interjob communication (IJC) devices are a set of special device numbers that let you transfer information between two or more InterSystems IRIS processes. The processes can be either jobbed processes or interactive processes.

IJC devices work in pairs. You can have up to 256 IJC device pairs. You use even-numbered devices, called receivers, to read data. You use odd-numbered devices, called transmitters, to write data. Attempts to read from a transmitter or write to a receiver result in a <NODEV> error.

You issue I/O commands to IJC devices, just as to any other device. After issuing **OPEN** and **USE** commands to the device, a process can issue:

- **READ** commands to a receiver device
- **WRITE** commands to a transmitter device

Only one process at a time can have a device open.

Pairs are based on relative order as mapped in the InterSystems IRIS Device Table, which you can view and edit using the configuration options of the Management Portal.

Each pair of devices is associated with an IJC memory buffer. When a process issues a **WRITE** command to any odd-numbered IJC device, InterSystems IRIS writes the data into the buffer for that device pair. When another process issues a **READ** command to the even-numbered device from that pair, InterSystems IRIS reads the data from the same buffer.

Written data is buffered in memory in first-in, first-out fashion. If a **READ** occurs while the device is empty, the process that issued it suspends until another process issues a corresponding **WRITE**. A **WRITE** that occurs while the buffer is full suspends until another process reads from that buffer.

After you write a message to the buffer, it remains there until it is read, even if you close the transmitter. Several users can issue **OPEN**, **USE**, **WRITE**, and **CLOSE** commands to a transmitter, one at a time in turn. Subsequent **READ** commands get all of the messages in the order in which they were written.

5.2 Specifying Memory Buffers for Interjob Communication Devices

The system manager can configure the IJC buffers using the Management Portal. Select **System Administration, Configuration, Additional Settings, Advanced Memory**. The two parameters that can be set are:

- **ijcnum**: The maximum number of IJC devices. The range is from 0 through 256. The default is 16. If you edit this setting, you must restart InterSystems IRIS to apply the change.
- **ijcbuf**: The maximum size (in bytes) of each IJC buffer. The range is from 512 through 8192. The default size is 512 bytes. If you edit this setting, you must restart InterSystems IRIS to apply the change.

Each IJC device corresponds to one IJC buffer of the size specified in **ijcbuf**. You can write a message of length **ijcbuf** minus 1.

5.2.1 Disabling Interjob Communication Buffers

If you will not be using IJC devices, you can set the maximum number of IJC devices (**ijcnum**) to 0 to avoid tying up memory.

5.3 Interjob Communication Device Numbers

Interjob communication devices are automatically defined numbered by InterSystems IRIS. Their actual identification numbers depends on the maximum number of IJC buffers configured on the system.

The table below gives the ranges of IJC device numbers that are available on your system, depending on the number of IJC buffers that you have allocated.

For example, if you allocate 8 IJC buffers, then device numbers from 224 through 239 are defined on the system (even numbers for **READ** devices and odd numbers for **WRITE** devices).

As another example, if you allocate 94 IJC buffers, then the following range of device numbers are defined: 224 through 255, 64 through 199, 4 through 19, and 2048 through 2051. You can use any even/odd number pairs with **OPEN**, **USE**, **READ**, **WRITE**, and **CLOSE** commands.

Table 5–1: IJC Device Numbers

Buffers Allocated	READ Device #	WRITE Device #
1	224	225
2	226	227
3	228	229
...	...	
15	252	253
16	254	255
17	64	65
18	66	67

Buffers Allocated	READ Device #	WRITE Device #
...
83	196	197
84	198	199
85	4	5
86	6	7
87	8	9
88	10	11
89	12	13
90	14	15
91	16	17
92	18	19
93	2048	2049
94	2050	2051
95	2052	2053
...
254	2370	2371
255	2372	2373
256	2374	2375

5.4 I/O Commands for IJC Devices

You use all of the standard I/O commands with IJC devices: **OPEN**, **USE**, **READ**, **WRITE**, and **CLOSE**.

5.4.1 OPEN Command

The **OPEN** command reserves interjob communication devices for your use.

```
OPEN device::timeout
```

where:

device

A device number from the table above. **OPEN** an even-numbered device to issue **READ** commands. **OPEN** an odd-numbered device to issue **WRITE** commands. For two processes to communicate, they must open a set of device pairs.

timeout

Optional — A positive integer whose value in seconds is the longest time InterSystems IRIS waits for an **OPEN** to finish. If you specify 0, the **OPEN** returns control to the process immediately.

This example shows how two processes communicate by opening separate devices for reading and writing:

```
Process A          Process B
OPEN 227 USE 227 WRITE "MSG_1"
WRITE "MSG_2"      OPEN 226 USE 226 READ X
CLOSE 227          CLOSE 226
OPEN 224 USE 224 READ X
CLOSE 224         WRITE X
WRITE X           MSG_1
MSG_3            .
                .
                .
                OPEN 225 USE 225 WRITE "MSG_3"
                CLOSE 225
```

Process A begins by opening device 227 and writing MSG_1 to it. InterSystems IRIS writes this message into the buffer shared by devices 226 and 227. Process A then writes a second message to the same buffer. Now Process B opens companion device 226 and reads the first message (MSG_1) from the buffer.

Now Process A wants to read a message, so it must open a different device, 224. Because the buffer for this device and its companion, 225, is currently empty, Process A waits until Process B opens device 225 and writes MSG_3 to it. After InterSystems IRIS places this message in the buffer shared by devices 224 and 225, the **READ** command to device 224 succeeds.

5.5 See Also

- [TCP Client/Server Communication](#)
- [TCP Advanced Topics](#)
- [UDP Client/Server Communication](#)
- [Local Interprocess Communication \(Pipes\)](#)

6

TCP Client/Server Communication

This page describes how to set up remote communication between InterSystems IRIS® data platform processes using TCP/IP.

6.1 Introduction

To create a client-server relationship between systems, you must follow a particular set of conventions:

- Your systems must be connected with appropriate networking hardware and software, including TCP/IP protocol software.
- Systems communicate with each other through a TCP port. The processes at both ends of the connection must use the same port number.
- You specify either the TCP port number, or the *devicename* of the device that represents it, as the device in InterSystems IRIS **OPEN**, **USE**, and **CLOSE** commands.

Using these conventions, the general procedure of establishing a TCP binding connection is:

1. The server process issues an **OPEN** command to a TCP device.
2. The server process issues a **USE** command, followed by a **READ** command, awaiting input from the client process. The server must be listening before a client can establish a connection. The initial **READ** command completes when the client has opened the connection and sent some data. You can include the A mode parameter in the **OPEN** command to make the initial **READ** complete as soon as the server accepts the connection.
3. The client process issues an **OPEN** command that specifies the TCP device to which it is connecting.
4. The client process issues a **USE** command followed by a **WRITE** command to complete the connection. InterSystems IRIS copies all characters in the **WRITE** command(s) to a buffer. It does not write them to the network until you issue a **WRITE !** or **WRITE #** command to flush the buffer.
5. After the server has read the characters that the client sent in its first **WRITE** command, both sides can continue to issue **READ** and **WRITE** commands. There is no further restriction on the order of these commands to the same port.
6. Either side can initiate the closing of a connection with the **CLOSE** or **HALT** command. Closing the client side first is preferable. If the server needs to disconnect so that it can accept a connection from another client process, it can instead issue a **WRITE *-2** command.

Note: This procedure assumes that both the client and server are InterSystems IRIS processes (though either process can be a non-InterSystems IRIS process).

The following sections detail how to use InterSystems IRIS I/O commands to create a TCP binding between client and server processes.

6.2 OPEN Command for TCP Devices

Both server and client processes use the ObjectScript **OPEN** command to initiate a connection. The server completes the connection by issuing a **READ** command, which receives the client **OPEN** command and first data transmission.

Note: If you issue an **OPEN** command on a TCP device that has already been opened, this second **OPEN** command is treated as a **USE** command. That is, the *hostname* and *port* parameters are ignored (retaining the first **OPEN** command values) and the *mode* and *terminators* parameters are updated.

6.2.1 Using the OPEN Command

The **OPEN** command reserves a TCP binding device for your use. The syntax is:

```
OPEN devicename:parameters:timeout:mnespace
```

where:

devicename

A string of the form |TCP| followed by some number of numeric digits. The numeric portion of the device name is called the device identifier. If the port number is not specified in the **OPEN** parameters, this device identifier must be a unique five-digit TCP port number. If the port number is specified in the **OPEN** parameters (which is the preferred practice), this device identifier can be any unique number (up to a maximum of 2147483647), so long as all the TCP device names used by a single job are distinct.

parameters

Optional — A series of one or more device parameters, enclosed by parentheses and separated by colons (:). If a parameter is omitted, specify the colon separator for the missing parameter. (For a server-side **OPEN** the first parameter is always omitted.) The specific parameters are described below.

If you specify only the first parameter (*hostname*), you can omit the parentheses. For example, the client-side open: `OPEN " |TCP| 7000" : "127.0.0.1" : 10`. If you specify no parameters, you can omit the parentheses, but you must retain the colon as a separator character. For example, the server-side open: `OPEN " |TCP| 7000" :: 10`.

timeout

Optional — Maximum number of seconds InterSystems IRIS attempts to open the TCP device. If it does not succeed within this interval, it sets **\$TEST** to 0 and returns control to the process. If it succeeds, it sets **\$TEST** to 1. Including a timeout in **OPEN** commands from the client prevents the client system from hanging if it tries to open a connection while the server is busy with another client. The server can have only one connection open at a time.

mnespace

Optional — Supported as it is for all ObjectScript **OPEN** commands. There is no predefined mnemonic space for TCP bindings.

If you omit an **OPEN** argument, you can indicate its absence by specifying the colon separator.

The *timeout* argument, though optional, is strongly recommended because the success or failure of **OPEN** is indicated by the value of the **\$TEST** special variable, and **\$TEST** is only set if *timeout* is specified. **\$TEST** is set to 1 if the open attempt succeeds before the timeout expires; if the timeout expires, **\$TEST** is set to 0.

If a TCP connection attempt fails on Windows systems, the TCP connection error is written to the InterSystems IRIS system error log (see [InterSystems IRIS System Error Log](#)), for example, error code 10061 = WSAECONNREFUSED.

The following is an example of a client-side **OPEN**, where 7000 is the port number and "127.0.0.1" is the *parameters* argument (the *hostname*, specified as an IPv4 address):

ObjectScript

```
SET dev="|TCP|7000"
OPEN dev:("127.0.0.1":7000)
```

6.2.1.1 hostname Parameter

The *hostname* parameter is required for a client-side **OPEN**. The client-side *parameters* argument may be just the *hostname*, or the *hostname* followed by other colon-separated parameters. If you specify just the *hostname* parameter, you can omit the *parameters* parentheses.

The server-side *parameters* argument omits the *hostname*.

The *hostname* can be either the name of an IP host (from the local system's database of remote hosts) or an IP address in either IPv4 or IPv6 protocol format. Because these protocols are incompatible, both the server and the client must use the same Internet protocol or the transmission will fail.

An IPv4 address has the following format. *n* is a decimal integer in the range 0 through 255:

n.n.n.n

An IPv6 address has the following full format. *h* is a hexadecimal number with four hexadecimal digits:

h:h:h:h:h:h:h:h

Commonly, IPv6 addresses are abbreviated by eliminating leading zeros and replacing consecutive sections of zeros with a double colon (::); only one double colon may be used in an IPv6 address. By using IPv4 abbreviation rules, you can specify the IPv6 loopback address as ":::1" (meaning that the first seven consecutive *h* sections all have the value 0000, and the leading zeros from the eighth section are eliminated).

You can use the **OPEN** keyword **/USEIPV6** to specify which protocol to use. Further details on IPv4 and IPv6 formats can be found in [Use of IPv6 Addressing](#).

6.2.1.2 Supported Parameters

The *parameters* argument can be in either of the following formats:

hostname

```
(hostname{:port{:mode{:terminators{:ibufsiz{:obufsiz{:queueize{:keepalivetime}}}}}}})
```

The parameters within the *parameters* argument are as follows:

hostname

Optional — Either the name of an IP host, an IP address in IPv4 protocol format, or an IP address in IPv6 protocol format. Specified as a quoted string. A *hostname* is required for a client-side **OPEN**; omitted (represented by a placeholder colon) for a server-side **OPEN**.

port

Optional — If present, this is the TCP port number to use for the connection. If this port number is null or omitted, then the port number is derived from the numeric portion of the *devicename*. This parameter can either be a decimal port number or a service name, which is submitted to the local system's TCP service name resolver.

mode

Optional — A string of letter code characters enclosed in quotes. Letter codes may be specified in any order; because InterSystems IRIS executes them in left-to-right order, interactions between letter codes may dictate a preferred order in some cases. The default is [packet mode](#). A *mode* string can consist of one or more of the following letter codes:

- A — Accept mode. If A is on, the initial read on the server terminates with a zero-length string as soon as the connection from the client job is accepted. If A is off, the read blocks until the timeout is reached, or until data is available, whichever occurs first.
- C — See [Carriage Return Mode](#) below.
- D — See [Monitoring for Disconnect Mode](#) below.
- E — See [Escape Sequence Processing Mode](#) below.
- G — Causes the *port* parameter to be interpreted as the socket descriptor of an already opened data socket.
- M — Standard InterSystems IRIS device in stream mode. This mode is a shorthand for invoking the `PSTE` set of options. It yields a device that acts like a standard InterSystems IRIS device that can be used to pass arbitrary lines of data in both directions. You turn on stream mode so that you can send or receive any arbitrary sequence of strings, without overrunning the buffers. Line feeds are added to output and stripped from input. **READ** commands block until one of the following occurs: a terminator character is seen, the timeout is reached, or the read length specified has been filled.
- P — Pad output with record terminator characters. When this mode is set, `WRITE !` sends LF (line feed) and `WRITE #` sends FF (form feed), in addition to flushing the write buffer. The `WRITE *-3` command can be used to initiate the sending of buffered data without inserting any characters into the data stream. Note that `WRITE *-3` just flushes the write buffer without sending any terminator character, and thus does not signal the recipient program that the data is complete. `WRITE *-3` is more commonly used in Wait (W) mode, which does not require a terminator.
- Q — See [Send Immediate Mode](#) below.
- S — See [Stream Mode](#) below.
- T — Standard terminators on input. When this is set, the CR, LF, and FF control characters function as read terminators.
- W — Wait mode. In this mode, `WRITE !` and `WRITE #` commands will not cause a TCP device to flush the network output buffers. Wait mode causes a TCP device to wait until the next `WRITE *-3` command to flush the buffers and transmit the data.

terminators

Optional — A list of up to eight user terminator characters that will terminate reads on the TCP binding device. If you specify both T mode and *terminators* at the same time, T mode is ignored.

ibufsiz

Optional — [Input buffer size](#). Internally, characters that have been read from the network but not yet delivered to the InterSystems IRIS program are buffered in a data area that can hold *ibufsiz* bytes.

obufsiz

Optional — **Output buffer size**. The maximum amount of data the TCP device can buffer between successive SEND operations. A SEND operation means to send the buffered data out to the network. WRITE !, WRITE #, and WRITE *-3 commands can generate SEND operations.

When S mode is specified, SEND operations are generated automatically to send the contents of the output buffer whenever it gets too full. When done creating a message, however, the programmer must still use one of the SEND operations to make sure the message is sent.

When S mode is not specified, if a **WRITE** operation would place enough data in the buffer to exceed the output buffer size, then a <WRITE> error occurs. Note that attempting to write a string that is in itself longer than the output buffer size always fails.

queuesize

Optional — An integer that specifies how many client jobs can queue for a connection to the server. Used for server-side **OPEN** only. The default is 5. The maximum value depends on the TCP implementation, but cannot exceed 1000.

keepalivetime

Optional — (Windows, AIX, and Linux only) Allows you to set a keepalive timer for this device that is different than the system default. Specify an integer number of seconds to keep alive the TCP connection. Valid values range from 30 to 432000. (432000 seconds is 5 days.) A value less than 30 defaults to 30. If omitted or set to 0, the system-wide default keepalive timer is used. See the [/KEEPALIVE keyword option](#) for further details.

The keepalive timer does not necessarily start timing when the TCP device is opened. It typically begins timing when the connection has been established. That is, when the initial read-for-connect has completed successfully.

6.2.1.3 Packet Mode

Packet mode is the default if no *mode* is specified. If [stream mode](#) is disabled, the mode defaults to packet mode.

In packet mode **READ** commands complete as soon as there is some data to return. Packet mode allows you to build an entire TCP segment in the output buffer, and then send it all at one time by issuing a WRITE *-3 or WRITE ! command.

If you issue WRITE *-1 to initiate a TCP SEND operation when there are no characters to be sent, you receive a <WRITE> error. If you issue **WRITE** of an empty string, you receive a <COMMAND> error.

The maximum size of the string you can send in packet mode is 1024 characters. If you exceed this limit without flushing the buffer, you receive a <WRITE> error.

Because TCP/IP ignores records with a length of 0, you receive a <WRITE> error if you flush the write buffer when there are no characters in it.

A **WRITE** command from server to client before the server has received a connection request produces a <WRITE> error on the server.

6.2.1.4 Carriage Return Mode (C mode)

This mode modifies processing of carriage returns on input and output.

On Output, WRITE ! generates CR LF and WRITE # generates CR FF.

On input, with T mode enabled, the server tries to record an adjacent CR and LF or an adjacent CR and FF as a single terminator in **\$ZB**. CR and LF are processed as separate terminators if they do not arrive within a short interval of each other. By default, the interval is 1 second.

6.2.1.5 Monitoring for Disconnect Mode (D mode)

This mode turns on or off asynchronous disconnect monitoring. This mode is activated by specifying the “D” mode character, or the /POLL or /POLLDISCON keyword parameter. When you specify +D, TCP disconnect monitoring is activated; when you specify -D, TCP disconnect monitoring is deactivated.

While activated, InterSystems IRIS polls the TCP connection roughly every 60 seconds. When it detects a disconnect, InterSystems IRIS issues a <DISCONNECT> error. Disconnect detection does not occur in idle jobs, such as a job suspended by a **HANG** command or a job waiting on a **READ** operation. InterSystems IRIS suspends all disconnect monitoring during a rollback operation to prevent a <DISCONNECT> error being issued. InterSystems IRIS resumes disconnect monitoring once the rollback concludes. This suspension applies both to a current TCP device with disconnect monitoring activated, and to a current device without disconnect monitoring that is connected to a TCP device with disconnect monitoring activated.

You can also check for TCP disconnect by using the **Connected()** method of the %SYSTEM.INetInfo class.

6.2.1.6 Escape Sequencing Processing Mode (E mode)

When the E mode is set, escape sequences in the input stream are parsed and placed into the **\$ZB** special variable. Escape sequences must be 15 characters or less and must match the following syntax:

```
esc_seq ::= type1 | type2
```

where:

```
type1 ::= '[' ['0' : '?' ] * [ ':' '/' ] * { '@' : DEL }
type2 ::= [ ';' | '?' | 'O' ] [ ':' '/' ] * { '0' : DEL }
```

The syntactic symbols used here mean:

Symbol	Description
:	x:y means a specified range of characters from x through y in the ASCII sequence.
	x y means specify either x or y.
[]	Specify zero or one members of the specified set.
[]*	Specify zero, one, or more members of the specified set.
{ }	Specify exactly one member of the specified set.

When InterSystems IRIS sees an ESCAPE, it waits up to 1 second for the rest of the escape sequence to arrive. If the escape sequence does not match this syntax, or if it is longer than 15 characters, or if a valid escape sequence does not arrive within 1 second, InterSystems IRIS places the partial escape sequence in **\$ZB** and sets the **BADESC** bit (256) in **\$ZA**.

6.2.1.7 Send Immediate Mode (Q mode)

In send immediate mode, each **WRITE** command is output as its own packet. If you are not using send immediate mode, you must either include a terminator or issue the command **WRITE * -3** to output a packet.

This mode is entered by specifying the “Q” mode character, or the /SENDIMMEDIATE (or /SEN) keyword parameter. To turn this option off, specify either of the following:

ObjectScript

```
USE TCPDEVICE: ( /SEN=0 )
USE TCPDEVICE: ( : : "-Q" )
```

To turn this option back on, specify either of the following:

ObjectScript

```
USE TCPDEVICE: ( /SEN=1 )
USE TCPDEVICE: ( : : "+Q" )
```

Send Immediate Mode, which creates one packet per write, is used in combination with /NODELAY mode, which immediately sends each packet as it is created. When both are on, the speed of transmission of a single burst of data is maximized. This is useful when timely delivery of each unit of data is critical, for example, in transmitting mouse movements. When both are off, a packet may contain multiple writes, and a transmission may contain multiple packets. This reduces network traffic and improves overall performance. The default for Send Immediate Mode is off. The default for /NODELAY mode is on.

6.2.1.8 Stream Mode (S mode)

In stream mode, InterSystems IRIS does not attempt to preserve TCP message boundaries in the data stream. On sending, if the data does not fit in the message buffer, InterSystems IRIS flushes the buffer before placing the data in it.

On receiving, data up to the maximum string length can be received. All reads wait for the full timeout for terminators to be reached or for the buffer to become full. When this mode is disabled (the default), you are in [packet mode](#).

Jobbed processes that inherit TCP devices are automatically set to Stream format. You can reset the format with the **USE** command.

6.2.1.9 Buffer Sizes

The *ibufsiz* and *obufsiz* parameters for TCP devices specify the sizes of the internal InterSystems IRIS buffers for TCP input and output. They can take values between 1KB and 1MB on all supported platforms. However, operating system platforms may use different sizes for their own input and output buffers. If the operating system platform buffer is smaller than the InterSystems IRIS buffer (for example, 64KB vs 1MB), performance may be affected: a WRITE operation may require several trips to the OS to send the entire InterSystems IRIS buffer; a READ operation may return smaller chunks that are limited by the OS buffer size. For optimal performance, a user should experiment with the current OS to determine which values for *ibufsiz* and *obufsiz* produce optimal results.

6.2.2 Server-Side OPEN Command

When the server-side **OPEN** is processed, it establishes a TCP socket and listens on the socket for incoming connection requests on the appropriate port number. The port number is either specified explicitly in the parameter list, or derived from the numeric portion of the *devicename*. The **OPEN** returns immediately after the socket has been set up to listen.

If the **OPEN** does not succeed, another process may already be listening for connection requests on that port number.

The following example of a server-side **OPEN** shows a device specification that allows reading and writing of terminated strings up to the maximum string size, and uses maximum length read and write operations to consolidate use of the TCP channel.

ObjectScript

```
OPEN " |TCP| 4" : ( : 4200 : "PSTE" : : 32767 : 32767 )
```

The *parameters* argument in this example is as follows: because this is a server-side **OPEN**, the first parameter (*hostname*) is omitted. The second parameter explicitly specifies the port number (4200). The third parameter is the *mode* code characters. The fourth parameter (*terminators*) is omitted. The fifth parameter is the input buffer size. The sixth parameter is the output buffer size.

In the following example the port number is not specified as a parameter; it is derived from the numeric portion of the *devicename*. This example opens port 4200 with no specified parameters and a timeout of 10 seconds:

ObjectScript

```
OPEN " |TCP|4200"::10
```

A server-side **OPEN** has default input buffer size (*ibufsiz*) and output buffer size (*obufsiz*) parameter values of 1,048,576 bytes (1 MB).

A server-side **OPEN** supports the optional *queuesize* parameter, and the optional **G** mode parameter. These options are not available to a client-side **OPEN**.

A server-side **OPEN** supports the optional **/CLOSELISTEN** keyword parameter. This option is not available to a client-side **OPEN**.

6.2.3 Client-Side OPEN Command

A client-side **OPEN** command differs from the server-side **OPEN** command in only one respect: the first device parameter must specify the host to which you are connecting. To specify the host, you include either a name that the client recognizes as a host, or an Internet address.

The **OPEN** succeeds as soon as the connection is established. At this point, you can read or write to the TCP device. However, if the server side of the connection is another InterSystems IRIS process, the server does not complete its side of the connection until some data has been sent from the client to the server with the **WRITE** command. Therefore, you must issue a **WRITE** command before you issue any **READ** commands.

For details, see [WRITE Command for TCP Devices](#).

Some examples of client-side **OPEN** commands are:

ObjectScript

```
OPEN " |TCP|4":( "hal":4200:: $CHAR(3,4) ):10
```

This command opens a connection to host `hal` on port 4200. It specifies no mode string. It specifies two terminators (ASCII `$CHAR(3)` and `$CHAR(4)`), and default input and output buffer sizes. It specifies a timeout of 10 seconds.

The following command is the same as the previous one, except that the destination is an explicit IP address in IPv4 format.

ObjectScript

```
OPEN " |TCP|4":( "129.200.3.4":4200:: $CHAR(3,4) ):10
```

You can use the **OPEN** keyword **/USEIPv6** to specify which protocol to use. Further details on IPv4 and IPv6 formats can be found in [Use of IPv6 Addressing](#).

The following command connects to time-of-day server on remote host `larry` and prints the remote host's time of day in ASCII format on the principal input device. It uses the service name `daytime`, which the local system resolves to a port number:

ObjectScript

```
OPEN " |TCP|4":( "larry": "daytime": "M" )
USE " |TCP|4"
READ x
USE 0
WRITE x
```

The following command sets `x` to `hello`:

ObjectScript

```
OPEN " |TCP|4":("larry":"echo":"M")
USE " |TCP|4"
WRITE "hello",!
READ x
```

The following command opens a connection to Internet address 128.41.0.73, port number 22101, with a 30-second timeout.

ObjectScript

```
OPEN " |TCP|22101":("128.41.0.73":30
```

6.2.4 OPEN and USE Command Keywords for TCP Devices

You can either use positional parameters (as described above) or keyword parameters. The following list describes the keywords for controlling TCP devices with both **OPEN** and **USE** commands. There are additional [OPEN-only keywords](#) that can only be specified in the **OPEN** command. All keyword parameters are optional.

/ABSTIMEOUT[=*n*]

Default: 0

Specifies read timeout behavior. Determines whether TCP should reinitialize the timeout period when data is received. If **/ABSTIMEOUT=0** (the default) timeout is reset to its original value each time data is received. If **/ABSTIMEOUT** or **/ABSTIMEOUT=1** the timeout period continues to count down while data is received.

/ACCEPT[=*n*]

Or:

/ACC[=*n*]

Default: 0

Corresponds to the A mode parameter character, which specifies that the initial read on the server terminates with a zero length string as soon as the connection from the client job is accepted. **/ACCEPT** and **/ACCEPT=*n*** for nonzero values of *n* enable A mode. **/ACCEPT=*n*** for a zero value of *n* disables A mode.

/CLOSEFLUSH[=*n*]

Default: 1

Specifies handling of data remaining in the output buffer when the device is closed. **/CLOSEFLUSH** and **/CLOSEFLUSH=*n*** for nonzero values of *n* flushes remaining data. **/CLOSEFLUSH=*n*** for a zero value of *n* discards remaining data.

/COMPRESS=*str*

Default: ""

Specifies the stream data compression type. You can enable a compression type of ZLIB or ZSTD. You can specify **/COMPRESS=""** to disable compression. **/COMPRESS="zlib"** is equivalent to **/GZIP=1**. To compress a string, use **%SYSTEM.Util.Compress()**.

/CRLF[=*n*]

Default: 0

Corresponds to the C mode parameter character, which modifies processing of carriage returns on input and output. **/CRLF** and **/CRLF=*n*** for nonzero values of *n* enable C mode. **/CRLF=*n*** for a zero value of *n* disables C mode.

/ESCAPE[=*n*]

Or:

`/ESC[=n]`

Default: 0

Corresponds to the `E` mode parameter character, which specifies that escape sequences in the input stream are parsed and placed into `$ZB`. `/ESCAPE` and `/ESCAPE=n` for nonzero values of *n* enable E mode. `/ESCAPE=n` for a zero value of *n* disables E mode.

/GZIP[=*n*]

Default: 1

Specifies GZIP-compatible stream data compression. `/GZIP` or `/GZIP=n` (for nonzero values of *n*) enables compression on WRITE and decompression on READ. `/GZIP=0` disables compression and decompression. Before issuing `/GZIP=0` to disable compression and decompression, check the `$ZEOS` special variable to make sure that a stream data read is not in progress. `/GZIP` compression has no effect on I/O translation, such as translation established using `/IOTABLE`. This is because compression is applied after all other translation (except encryption) and decompression is applied before all other translation (except encryption). For further information on WRITE with compressed data, see [WRITE Control Characters](#).

/IOTABLE[=*name*]

Or:

`/IOT[=name]`

Default: If *name* is not specified, the default I/O translation table for the device is used.

Establishes an I/O translation table for the device.

/KEEPALIVE=*n*

Default: system default

(Windows, AIX, and Linux only) Allows you to set a keepalive timer for this device that is different than the system default. An integer that specifies the number of seconds to keep alive the TCP connection. Same as the *keepalivetime* positional parameter. Valid values range from 30 to 432000. (432000 seconds is 5 days.) A value less than 30 defaults to 30. If omitted or set to 0, the system default is used. This setting can be disabled using `/NOKEEPALIVE`; once disabled, it cannot be re-enabled until this TCP device is closed.

/NODELAY=*n*

Default: 1

Specifies whether packets should be bundled or sent individually. If `/NODELAY=1` (the default) each packet is immediately transmitted. If `/NODELAY=0` the TCP driver bundles packages together using an optimization algorithm. This can cause a slight transmission delay for an individual packet, but by reducing network traffic it can improve overall performance. `/NODELAY` has no corresponding mode parameter character. Use of `/NODELAY` should be coordinated with use of [/SENDIMMEDIATE](#).

/NOKEEPALIVE

If specified, the system-wide TCP keepalive timer is disabled for this device. InterSystems IRIS enables this timer by default when opening any TCP device; issuing the `/NOKEEPALIVE` option on OPEN or USE overrides this default. If `/KEEPALIVE` has been used to set a non-default keepalive timer, `/NOKEEPALIVE` disables that keepalive timer. Once you disable a keepalive timer there is no way to re-enable it until the TCP device is closed. See `/KEEPALIVE`.

/NOXY[=*n*]

Default: 0

No \$X and \$Y processing: /NOXY or /NOXY=*n* (for nonzero values of *n*) disables \$X and \$Y processing. This option can improve performance when device \$X/\$Y is not used, for example with CSP. It can substantially improve performance of READ and WRITE operations. This option is the default setting for superserver worker jobs. When /NOXY=1, the values of the \$X and \$Y variables are indeterminate, and margin processing (which depends on \$X) is disabled. /NOXY=0 enables \$X and \$Y processing; this is the default. /TCPNOXY is a deprecated synonym for /NOXY.

/OBCOUNT=*n*

Default: 16

The number of output buffers to use with /ZEROCOPY. The default number of output buffers is 16. The minimum number of output buffers is 2 and the maximum is 128. The value of *n* must be power of 2; if a non-power-of-2 value is specified, it is rounded up to a power of 2.

/PAD[=*n*]

Default: 0

Corresponds to the P mode parameter character, which specifies that output is padded with record terminator characters when WRITE ! (LF terminator) or WRITE # (FF terminator) is executed. /PAD and /PAD=*n* for nonzero values of *n* enable P mode. /PAD=*n* for a zero value of *n* disables P mode.

/PARAMS=*str*

Or:

/PAR=*str*

No default. Corresponds to the *mode* positional parameter. (It provides a way to specify a mode string in a position-independent way.)

/POLL[=*n*]

Or:

/POLLDISCON[=*n*]

Corresponds to the D mode parameter character, which specifies asynchronous monitoring for disconnect. /POLL or /POLL=1 corresponds to +D. /POLL=0 corresponds to -D.

/PSTE[=*n*]

Default: 0

Corresponds to the M mode parameter character, which is a shorthand way to specify the P, S, T and E mode parameter characters. /PSTE and /PSTE=*n* for nonzero values of *n* enable P, S, T and E modes. /PSTE=*n* for a zero value of *n* disables these modes.

/SENDIMMEDIATE[=*n*]

Or:

/SEN[=*n*]

Default: 0

Corresponds to the Q mode parameter character, which specifies [Send Immediate Mode](#).

/SSL="cfg[|pw] [|DNShost]"

Or:

```
/TLS="cfg[|pw] [|DNShost]"
```

No default.

From a client, specifies that the device attempts to negotiate an SSL/TLS-secured connection according to the client's specified configuration and server requirements. When securing a socket as a server, specifies that the server requires a SSL/TLS-secured connection according to the server's specified configuration and any client requirements.

The value of the /SSL or /TLS keyword parameter is a quoted string. This string can have one, two, or three components, separated by the '|' character:

- *cfg* specifies the name of the configuration for the connection or socket. *pw* specifies the optional private key file password. *DNShost* specifies the fully qualified DNS hostname of a specific server, for use with the Server Name Indication (SNI) TLS extension.

This configuration name is used only the first time I/O is performed after the **OPEN** or **USE** command. Subsequent invocations are ignored. /SSL=" " or /TLS=" " is ignored. For more information, see [InterSystems TLS Guide](#).

- *pw* (*optional*) is the password for the local private key file. This is intended for interactive applications only, when a user is being prompted to enter the password at run time. It should not be used with a persistently stored password. Use the `Security.SSLConfigs.PrivateKeyPassword` property for persistent storage.

IMPORTANT: The ability to include a password when opening a new or securing an existing TCP connection using SSL/TLS is for real-time interactive use only. You should *never* store a private key password persistently without protecting it. If you need to store such a password, use the `PrivateKeyPassword` property of the `Security.SSLConfigs` class.

- *DNShost* (*optional*) for SSL clients only, specifies the fully qualified DNS hostname of a specific server (for Server Name Indication). If you omit *pw* you must specify the placeholder '|' character.

Server Name Indication (SNI) is a feature that allows the client to submit the hostname it's asking for to the server. This allows a server which handles multiple domains to select one of its multiple certificates to return. The server can select one which will match hostname checking on the client.

The following are examples of valid /TLS keyword parameters:

```
/TLS="Client"
/TLS="Client|password"
/TLS="Client|www.intersystems.com"
/TLS="Client|password|www.intersystems.com"
```

/STREAM[=n]

Or:

```
/STR[=n]
```

Default: 0

Corresponds to the *S* mode parameter character, which specifies a stream mode of handling data that does not preserve TCP message boundaries. /STREAM and /STREAM=*n* for nonzero values of *n* enable *S* mode. /STREAM=*n* for a zero value of *n* disables *S* mode.

/TCPNOXY

Deprecated. A synonym for /NOXY.

/TCPRCVBUF=*n*

Default: Default receive buffer size

Set receive queue buffer size, in bytes. Can be used to increase the buffer size from the default value to support TCP protocol large windows. Large windows improve performance over links with long latencies or very high bandwidth. For appropriate values, consult your OS/hardware documentation.

/TCPSNDBUF=*n*

Default: Default send buffer size

Set send queue buffer size, in bytes. Can be used to increase the buffer size from the default value to support TCP protocol large windows. Large windows improve performance over links with long latencies or very high bandwidth. For appropriate values, consult your OS/hardware documentation.

/TERMINATOR=*str*

Or:

`/TER=str`

No default.

Corresponds to the *terminators* positional parameter, which establishes user-defined terminators.

/TMODE[=*n*]

Or:

`/TMO[=n]`

Default: 0

Corresponds to the T mode parameter character, which specifies CR, LF, and FF as standard read terminators. `/TMODE` and `/TMODE=n` for nonzero values of *n* enable T mode. `/TMODE=n` for a zero value of *n* disables T mode.

/TRANSLATE[=*n*]

Or:

`/TRA[=n]`

Default: 1

`/TRANSLATE` or `/TRANSLATE=n` for nonzero values of *n* enable I/O translation for the device. `/TRANSLATE=n` for a zero value of *n* disables I/O translation for the device.

/WAIT[=*n*]

Default: 0

Corresponds to the W mode parameter character, which causes output buffers not to be flushed by the `WRITE !` and `WRITE #` commands. Rather, flushing waits until the next `WRITE *-3` command. `/WAIT` and `/WAIT=n` for nonzero values of *n* enable W mode. `/WAIT=n` for a zero value of *n* disables W mode.

/WRITETIMEOUT[=*n*]

Default: -1

Establishes a timeout (in seconds) for TCP write operations. If a write does not complete within *n* seconds, InterSystems IRIS issues a <TCPWRITE> error. If a <TCPWRITE> error is issued, your application should immediately close the TCP device to prevent data loss. InterSystems IRIS will not attempt a TCP write operation following a <TCPWRITE> error. The minimum *n* value is system-dependent. If *n* is smaller than the minimum timeout value for the platform, InterSystems IRIS uses the platform minimum. No *n* value should be less than 2. The default (-1) indicates no timeout is enforced.

/XYTABLE[=*name*]

Or:

/XYT[=*name*]

Default: If *name* is not specified, the default \$X/\$Y action table for the device is used.

Establishes a \$X/\$Y action table for the device. See /NOXY.

/ZEROCOPY[=*bool*]

Default: 0

If /ZEROCOPY or /ZEROCOPY=1 is specified, enable the ZEROCOPY feature for this TCP device. ZEROCOPY supports multiple output buffers for the TCP device in order to take advantage of MSG_ZEROCOPY on send(); the TCP device cannot re-use the output buffer until the buffer has been acknowledged by notification from the TCP stack. To set the number of output buffers for the TCP device use the /OBCOUNT keyword. If /ZEROCOPY=0 is specified, disable the ZEROCOPY feature for this TCP device. MSG_ZEROCOPY is supported in Linux 4.15 and later. If the operating system does not support MSG_ZEROCOPY, the ZEROCOPY of the TCP device is always disabled.

6.2.5 OPEN-Only Command Keywords for TCP Devices

The following list describes the keywords for controlling TCP devices that can only be specified in the **OPEN** command. There are additional [OPEN/USE keywords](#) that can be specified with either the **OPEN** or **USE** command. All keyword parameters are optional.

/BINDTO[=*address*]

Binds to a specified local address that is used when initiating connection. For client, this is the source address used when opening a TCP/IP connection from InterSystems IRIS. For server, this is the IP address that the InterSystems IRIS process will accept connections on when opening a TCP/IP connection. /BINDTO=*address* is used to control which network interface the connection will use. /BINDTO or /BINDTO="" deletes a previously specified address. If the specified *address* does not exist, the **OPEN** command will time out.

/CLOSELISTEN

(Server only) Prevents more than one remote connections to the listening port. If specified, the listen socket is closed after the first connection is accepted. Additional clients attempting to connect will time out on the **OPEN** command.

/CONNECTIONS=*n*

Or:

/CON=*n*

Default: 5

Corresponds to the *queuesize* positional parameter, which determines how many client jobs can queue for a connection to the server.

/HOSTNAME=*str*

Or:

*/HOS=*str**

No default.

Corresponds to the *hostname* positional parameter, which is either the name of an IP host or an IP address in IPv4 or IPv6 address format. You can use the */USEIPV6* keyword to specify which protocol to use. Further details on IPv4 and IPv6 formats can be found in [Use of IPv6 Addressing](#).

/IBUFSIZE=*n*

Or:

*/IBU[=*n*]*

Default: 1024

Corresponds to the *ibufsiz* positional parameter, which specifies the [size of the TCP input buffer](#) that holds data read from the network, but not yet delivered to the application.

/OBUFSIZE=*n*

Or:

*/OBU[=*n*]*

Default: 1024

Corresponds to the *obufsiz* positional parameter, which specifies the [size of the TCP output buffer](#) that contains data that is held between successive "SEND" operations.

/PORT=*n*

No default.

Corresponds to the *port* positional parameter, which is either the TCP port number or a service name to use for the connection.

/SOCKET=*n*

Or:

*/SOC=*n**

No default.

Corresponds to the *G* mode parameter character, which causes the *port* positional parameter to be interpreted as the socket descriptor of an already opened data socket. This keyword takes as its value that socket descriptor and is used instead of the */PORT=*n** keyword. (A socket descriptor is passed to ObjectScript from another programming environment, such as C, using the InterSystems IRIS Call-in or Call-out mechanisms.)

/USEIPV6

No default.

If */USEIPV6* or */USEIPV6=1* is specified, use an IPv6 address for both inbound and outbound connections, overriding the *IPV6* system switch. If */USEIPV6=0* is specified, use an IPv4 address for both inbound and outbound connections, overriding the *IPV6* system switch.

If /USEIPV6 is not specified, the IPV6 system switch governs behavior. With IPV6 system switch set, an outbound connection tries to connect with an IPv4 address first; if fails it tries to connection with an IPv6 address. For an inbound connection, the TCP device listens to both IPv4 and IPv6 connections. With IPV6 not set, only IPv4 addresses are used for both inbound and outbound connections.

The following example shows a TCP/IP device being opened using keyword syntax:

ObjectScript

```
SET dev="|TCP|"_123
SET portnum=57345
OPEN dev: (/PSTE:/HOSTNAME="128.41.0.73":/PORT=portnum)
```

6.3 Current TCP Device

You can return the IP address and port number of the current TCP device using the methods of the %SYSTEM.TCPDevice class. You can list these methods using the **Help()** method, as follows:

ObjectScript

```
DO $SYSTEM.TCPDevice.Help()
```

You can display information about a specific method by specifying the method name in **Help()**, as shown in the following example:

ObjectScript

```
DO $SYSTEM.TCPDevice.Help("LocalAddr")
```

6.4 USE Command for TCP Devices

The **USE** command issued from either the client or server lets you prepare to send or receive data using a TCP connection you previously opened. It has the following syntax (colons must be specified as shown):

```
USE devicename:(::mode:terminators)
```

Where:

devicename

A string of the form |TCP| followed by some number of numeric digits. The numeric portion of the device name is called the device identifier. If the port number is not specified in the **OPEN** parameters, this device identifier must be a unique five-digit TCP port number. If the port number is specified in the **OPEN** parameters (which is the preferred practice), this device identifier can be any unique number, so long as all the TCP device names used by a single job are distinct.

mode

Optional — **USE** supports the same mode parameters as **OPEN**. See [OPEN and USE Command Keywords for TCP Devices](#).

terminators

Optional — A list of up to eight user terminator characters that will terminate reads on the TCP binding device. It does not make sense to specify both T mode and user terminators at the same time, but if you do then T mode is ignored.

The simplest form of **USE** takes its mode and terminators parameters from the **OPEN** command, as shown in the following example:

ObjectScript

```
USE " |TCP|4"
```

You can replace, add, or delete mode parameters and user terminators after the device has been opened.

To replace the parameters specified in **OPEN**, specify replacement values in **USE**. In the following example, the **USE** command replaces the **OPEN** mode with PSTE mode and turns off any user terminators:

ObjectScript

```
USE " |TCP|4" : ( : : "PSTE" )
```

To add to or delete from the mode parameters specified in **OPEN**, use the + sign to introduce mode parameters that will be turned on, and the – sign to introduce mode parameters that will be turned off. If you do not specify either + or –, the new set of mode parameters replaces the existing mode parameters. In the following example, the **USE** command turns off Q mode (send immediate) and turns on W mode (wait). It leaves the rest of the mode string unchanged:

ObjectScript

```
USE " |TCP|4" : ( : : "-Q+W" )
```

In the following example, the **USE** command leaves the mode string unchanged and specifies a new set of user terminators.

ObjectScript

```
USE " |TCP|4" : ( : : "+" : $CHAR(3,4) )
```

6.5 READ Command for TCP Devices

Issue the **READ** command from either the server or the client to read any characters set by either the client or the server.

The syntax is as follows:

```
READ var:timeout
READ *var:timeout
READ var#length:timeout
```

The *timeout* argument, though optional, is strongly recommended because the success or failure of the **READ** is indicated by the value of the **\$TEST** special variable if *timeout* is specified. **\$TEST** is set to 1 if the read attempt succeeds before the timeout expires; if the timeout expires, **\$TEST** is set to 0.

The *timeout* argument supports seconds and fractions of a second to 1/100th of a second. For example, 10, 10.5, .5, .05.

For an SSL connection, a job can wait in the first read or first write command if the other party never issues a read or write command after the connection is established. In this circumstance, InterSystems IRIS supports the read timeout for a **READ** command and write timeout (with /WRITETIMEOUT=*n* option) for a **WRITE** command. If there is no read or write timeout specified, then the job will wait until the other party issue a read or write command.

You can determine the number of reads performed by the current TCP connection using the **TCPStats()** method of the **%SYSTEM.INetInfo** class.

6.5.1 READ Modifies \$ZA and \$ZB

Your application can learn about how the connection and read succeeded by testing the values of **\$ZA** and **\$ZB**.

6.5.1.1 \$ZA and READ Command

\$ZA reports the state of the connection. When the 0x1000 bit (4096) is set, this TCP device is functioning in Server mode. When the 0x2000 bit (8192) is set, the device is currently in the Connected state talking to a remote host.

For example, assume that a server-side TCP device is expected to accept a new TCP connection. By looking at **\$ZA** and **\$TEST** after an initial timed read, the InterSystems IRIS program can distinguish among three cases:

\$ZA Value	\$TEST Value	Meaning
4096	0	No connection has been accepted.
12288	0	Connection accepted, no data received.
12288	1	Connection accepted and data received.

The following table shows what each bit in **\$ZA** represents.

Decimal Value of \$ZA	Hexadecimal Value of \$ZA	Meaning
2	0x2	Read timed out.
4	0x4	I/O error.
256	0x80	Bad escape sequence received.
4096	0x1000	Server mode.
8192	0x2000	Connected.

6.5.1.2 \$ZB and READ Command

\$ZB holds the character that terminated the read. This character can be one of the following:

- A termination character, such as a carriage return
- The yth character of a fixed-length `READ x#y`
- The single character of `READ *X`
- An empty string after a timed read expires
- An escape sequence

Note that if a string is terminated with CR LF, then only the CR is placed in **\$ZB**.

6.6 WRITE Command for TCP Devices

The **WRITE** command sends data to a TCP device from the client or the server after you have established connection with **OPEN** and **USE**.

The syntax is as follows:

```
WRITE x
WRITE !
WRITE #
```

6.6.1 How WRITE Works

WRITE *x* sends *x* from the client or server to a buffer after the connection has been established.

WRITE ! and WRITE # do not indicate line and form feed. Instead, they tell InterSystems IRIS to flush any characters that remain in the buffer and send them across the network to the target system.

You can determine the number of writes performed by the current TCP connection using the `TCPStats()` method of the `%SYSTEM.INetInfo` class.

6.6.2 WRITE Modifies \$X and \$Y

InterSystems IRIS stores the number of characters in the buffer in the `$X` special variable.

The ASCII characters <return> and <line feed> are not included in this count, as they are not considered part of the record. Flushing the buffer with WRITE ! resets `$X` to 0, and increases the value of `$Y` by 1. Flushing the buffer with WRITE # writes the ASCII character <form feed> as a separate record, and resets `$Y` to 0.

6.6.3 WRITE Command Errors

You can receive a <WRITE> error in any of the following circumstances.

- If you exceed the maximum string size (1024 characters) without flushing the buffer.
- If you flush the write buffer when there are no characters in it (TCP/IP ignores records of 0 length).
- If you send a **WRITE** command from the server to the client before the server receives a connection request from client. (InterSystems IRIS produces the <WRITE> error on the server.)

6.6.4 WRITE Control Commands

The InterSystems IRIS TCP binding device supports a series of control commands with the `WRITE *-n` syntax.

Syntax	Description
WRITE *-2	On a server-mode session that is currently connected to a client, this command disconnects from the session. To accept a new session, you then execute a new READ command on the device.
WRITE *-3	Sends any buffered output out the TCP connection; that is, executes a TCP SEND operation on the data in the output buffer. If the data is compressed (/GZIP) stream data, *-3 sends the data without marking the compression endpoint. Resets <code>\$X</code> to 0. Increments <code>\$Y</code> by 1. If there is no buffered output, this command does nothing.
WRITE *-99	Sends compressed (/GZIP) stream data. First marks the data in the output buffer with a compression endpoint, then sends this compressed stream data by executing a TCP SEND operation on the output buffer data.

6.7 Closing the Connection

Either the client or the server can end a TCP binding connection. The preferred way to close a connection is for the client to issue a **CLOSE** command for the TCP device. (Alternatively, the client may issue **HALT** command.) The server should then issue another **READ** command to that device and receive a <READ> error, then issue a **CLOSE** command for the TCP device.

The reason for this sequence is that, in accordance with the TCP/IP standard, connection resources are maintained for two minutes after a **CLOSE**, but only for the “active closer” — the process that performs the **CLOSE** first. Thus it is preferable to close the client first, because the resources of the server are usually more limited than those of the clients.

6.7.1 Disconnect with CLOSE Command

Issue this form of the **CLOSE** command from the client or server:

```
CLOSE " |TCP|devicenum"
```

As stated above, it is preferable for the client to issue the **CLOSE** command first. If the server issues the **CLOSE** command first, the client gets a <WRITE> error and should then issue a **CLOSE** command.

6.7.1.1 JOBSERVER Resources

If you are writing an InterSystems IRIS server to interface with clients over which you have no control, the server process must issue the **CLOSE** to close the TCP connection. The **CLOSE** command does close the connection as far as InterSystems IRIS is concerned, but internally TCP/IP retains resources for this connection on the server for up to two minutes.

This can have unexpected results when JOBSERVERs are used to service TCP/IP jobs. When a JOBSERVER process performs a halt, the process immediately returns to the pool of available JOBSERVER processes, but its resources are retained internally for up to two minutes. Because JOBSERVER processes are assigned on a first-available basis, it is possible for a heavy load from a relatively small number of clients to exhaust the resources of a JOBSERVER process.

To avoid this problem, a TCP/IP server opened by a **JOB** running under a JOBSERVER should explicitly issue a **CLOSE**, and then issue a brief **HANG** before the final **QUIT** (or **HALT**) command. In accordance with TCP/IP specification, a **HANG 120** is required to guarantee no resources remain in use between incarnations in JOBSERVER. In practice, a **HANG** of one second is usually sufficient to evenly distribute resource load among JOBSERVER processes.

6.7.2 Automatic Disconnection

The TCP binding connection closes automatically under these conditions:

- An InterSystems IRIS fatal error
- RESJOB of the client or server process
- iris stop
- iris force

6.7.3 Effects of Disconnection

The effect of a disconnection on data remaining in the output buffer is determined by the /CLOSEFLUSH setting established during **OPEN** or **USE**. The default is to flush the data.

If one side closes a connection but the other side issues new **WRITE** commands, the first of these **WRITE** commands may succeed. Any additional **WRITE** commands receive a <WRITE> error.

From the client side, all **READ** commands to the side that closed the connection receive <READ> errors. The device must be closed and reopened to reestablish communication with the server.

From the server side, the first **READ** after a <READ> or <WRITE> error waits for and accepts a new connection.

You can use the `%SYSTEM.TCPDevice.GetDisconnectCode()` method to return the internal error that resulted in a <READ> or <WRITE> error on the current TCP device. \$IO must be a TCP device.

6.8 See Also

- [TCP Advanced Topics](#)
- [UDP Client/Server Communication](#)
- [Local Interprocess Communication \(Pipes\)](#)
- [Communication Between InterSystems IRIS Processes](#)
- [Use of IPv6 Addressing](#)

7

TCP Advanced Topics

This page discusses several advanced topics in communication between InterSystems IRIS® data platform processes using TCP/IP.

7.1 Connection Management

The server maintains only one connection at a time. If a second client tries to connect while another connection is open, TCP/IP places that client in a queue. While in the queue, the second client can write to the port as if it were connected. The data the second client writes remains in a buffer until the first connection is closed and the second client connects.

The second client hangs if it issues a **READ** before the connection exists. Any connection attempt by a third client while the second one is in the queue fails.


If a client that has already opened a TCP device tries to connect a second time while the first connection still exists, the second **OPEN** command causes a <COMMAND> error. Treating this situation as an error rather than as a **USE** command prevents surprising results. Such unexpected results could occur if an erroneous program thinks it has opened a new connection, when it is actually reusing an existing connection that may have a different destination or different parameters.

To handle multiple clients, see below.

7.1.1 Job Command with TCP Devices

You can use the **JOB** command to implement a *TCP concurrent server*. A TCP concurrent server allows multiple clients to be served simultaneously. In this mode, a client does not have to wait for the server to finish serving other clients. Instead, each time a client requests the server, it spawns a separate subjob for that client which remains open as long as the client needs it. As soon as this subjob has been spawned (indicated by the return of the **JOB** command), another client may request service and the server will create a subjob for that client as well.

Figure 7–1: Client/Server Connections in the Non-Concurrent and Concurrent Modes.



A concurrent server uses the **JOB** command with the *switch* concurrent server bit (bit 4 or bit 16) set. Bit 16 is the recommended setting.

- If bit 4 is set, the **JOB** command passes to the spawned process the TCP device in the *principal input* and *principal output* process parameters. Whenever you include bit 4 in *switch*, you must specify the TCP device in both *principal input* and *principal output* process parameters. You must use the same device for both *principal input* and *principal output*. Use of bit 4 is not recommended; see **JOB** command in the *ObjectScript Reference* for further details.
- If bit 16 is set, the **JOB** command passes to the spawned process three separate devices for the TCP device, the *principal input*, and *principal output* process parameters. You specify two of these TCP devices in the **JOB** command, using the *principal input* and *principal output* process parameters. You can also default these parameters, as shown in the following examples: `JOB child:(:16:input:output)` or `JOB child:(:16::)`.

See **JOB** command in the *ObjectScript Reference* for an example and further details.

Before you issue the **JOB** command, the device(s) you specify for principal input and principal output must:

- Be open
- Be listening on a TCP port
- Have accepted an incoming connection

After the **JOB** command, the device in the spawning process is still listening on the TCP port, but no longer has an active connection. The application should check **\$ZA** after issuing the **JOB** command to make sure that the **CONNECTED** bit in the state of the TCP device was reset.

The spawned process starts at the designated entry point using the specified TCP device. The TCP device has the same name in the child process as in the parent process. The TCP device has one attached socket. The inherited TCP device is

in S (stream) mode. However, the child process can change the mode with a **USE** command. We recommend that the server open TCP device in the A (accept) mode.

The TCP device in the spawned process is in a connected state: the same state the device would receive after it is opened from a client. The spawned process can use the TCP device with `USE 0` or `USE $P`. It can also use the TCP device implicitly (if `switch=4`). However, for the following reasons `switch=16` is preferable to `switch=4`:

- When `switch=4`, if a <READ> error occurs on the principal device, the job simply halts, without taking an error trap. This is because when `switch=4` the TCP device is the principal device. To support error trapping, use `switch=16` and specify another device for the TCP device.
- When `switch=4`, if the remote TCP device closes down the connection, the job simply halts, without taking an error trap. To override this default behavior and generate a <DSCON> error, you must set the **DisconnectErr()** method of the %SYSTEM.Process class.

You can use the %SYSTEM.Socket class methods, rather than the **JOB** command, to create concurrent TCP server connections. However, note that the %SYSTEM.Socket methods assume that the worker jobs are already started. You can use these methods for concurrent TCP server connections if you do not need the listener job to start the worker jobs, and the listener job knows Process IDs (PIDs) of the worker jobs.

7.2 Concatenation of Records

In certain situations, TCP concatenates separate records to form a single record. Concatenation can occur if a client or server process issues a series of **WRITE** commands to a TCP port, separated by `WRITE !` or `WRITE #` commands to flush the buffer, whether or not a **READ** command is waiting at the other end of the connection.

The first example below outlines how Process A receives two separate records when it has a **READ** command waiting as Process B writes two records to the TCP port.

```
Process A                               Process B
%SYS> USE "|TCP|41880" R A U O W A      %SYS> USE "|TCP|41880" WRITE "ONE",!, "TWO"
<RETURN>                                <RETURN>
ONE
%SYS> USE 41880 R A U O W A
<RETURN>
TWO
```

The second example outlines how Process A receives one concatenated record when it issues its **READ** command after Process B has finished writing two records to the TCP port.

```
Process A                               Process B
.                                         %SYS> USE "|TCP|41880" WRITE "ONE",!, "TWO"
.                                         <RETURN>
ONE
%SYS> USE "/TCP/41880" R A U O W A
<RETURN>
ONETWO
```

7.3 Multiplexing InterSystems IRIS TCP Devices

The %SYSTEM.Socket class provides methods for multiplexing InterSystems IRIS TCP devices. The **Fork()** and **Select()** methods allow you to have a single job handling both accepting new connections and reading data from a connected TCP device at the same time. After a listening TCP device received a connection, use **Fork()** to create a new TCP device for reading data. The original listening TCP device continues to accept incoming connections. You use the **Select()** method to

wait for both listening and connected TCP devices. When a new connection arrived or data becomes available, **Select()** returns the device name that was signaled.

You can use the **Select()**, **Publish()**, **Export()**, and **Import()** methods to have a listener job accept an incoming connection and pass the connected device to a worker job. This worker job could communicate with the remote client.

For further details and program examples, see %SYSTEM.Socket class in the *InterSystems Class Reference*.

7.4 See Also

- [TCP Client/Server Communication](#)
- [UDP Client/Server Communication](#)
- [Local Interprocess Communication \(Pipes\)](#)
- [Communication Between InterSystems IRIS Processes](#)
- [Use of IPv6 Addressing](#)

8

UDP Client/Server Communication

This page describes how to set up remote communication between processes using UDP.

8.1 Introduction

UDP is supported through the `%Net.UDP` class. This class provides methods to **Send()** a packet to a specified destination and port, to **Recv()** a packet from the socket, and to **Reply()** to the transmitter of the last received packet.

The destination is identified as a local host name or an IPv4 or IPv6 host address. The port can be either a specified port number or a dynamic port assignment.

8.2 Establishing a UDP Socket

To use UDP, you must use the `%New()` method to create a UDP socket object. This object instance is then used to send, receive, and reply to packet transmissions.

When you create a UDP socket object you can specify the port number and the host address, as shown in the following example:

ObjectScript

```
SET UPDoref=##class(%Net.UDP).%New(3001,"0.0.0.0")
```

Both the port number and the host address are optional. The `%New()` method returns the OREF (object reference) of the UDP socket object instance.

There are two sides to a UDP transmission:

- The server waits to receive a request and then provides the requested information. Thus this side of the transmission may be referred to as the Receiver or the Provider. When a provider creates an UDP object, it must define a port number on which it will receive requests.
- The client sends a request for information and then receives a reply. Thus this side of the transmission may be referred to as the Sender or the Requestor. When a requestor creates an UDP object, it can use a dynamic port number. The default is 0. When it sends a packet, it must specify the host name and port number of the provider.

8.3 The Host Address

The **Send()** method specifies the binary address of the destination. This is a binary version of the host address. You must create this binary host address by using the **GetHostAddr()** method, as follows:

ObjectScript

```
SET client=##class(%Net.UDP).%New()
SET addrbin=##class(%Net.UDP).GetHostAddr("172.16.61.196")
WRITE client.Send("message text",addrbin,3001)
```

You can specify a host name, an IPv4 address, or an IPv6 address to **GetHostAddr()**, as shown in the following examples:

ObjectScript

```
SET hostname="MYLAPTOP"
SET IPv4="172.16.61.196"
SET IPv6="::1"
SET flag=$SYSTEM.INetInfo.CheckAddressExist(hostname)
IF flag=1 { SET addrbin=##class(%Net.UDP).GetHostAddr(hostname)
            WRITE "host name valid",! }
            ELSE { WRITE "not a hostname: ",hostname,! }
SET flag=$SYSTEM.INetInfo.CheckAddressExist(IPv4)
IF flag=1 { SET addrbin=##class(%Net.UDP).GetHostAddr(IPv4)
            WRITE "IPv4 valid",! }
            ELSE { WRITE "not an IPv4 address: ",IPv4,! }
SET flag=$SYSTEM.INetInfo.CheckAddressExist(IPv6)
IF flag=1 { SET addrbin=##class(%Net.UDP).GetHostAddr(IPv6)
            WRITE "IPv6 valid",! }
            ELSE { WRITE "not an IPv6 address: ",IPv6,! }
```

You can expand this binary host address back to the host name using the **AddrToHostName()** method, as shown in the following example:

ObjectScript

```
SET addrbin=##class(%Net.UDP).GetHostAddr("MYLAPTOP")
WRITE $SYSTEM.INetInfo.AddrToHostName(addrbin)
```

You can use the **LocalHostName()** method to determine your host name. You can use the **HostNameToAddr()** method to translate a host name to an IPv4 or IPv6 address, as shown in the following example:

ObjectScript

```
SET localhost=$SYSTEM.INetInfo.LocalHostName()           /* get host name */
WRITE "local host name is ",localhost,!
SET addrbin=##class(%Net.UDP).GetHostAddr(localhost)    /* compress to binary address */
WRITE "binary form of IP address is ",addrbin,!
SET hostname=$SYSTEM.INetInfo.AddrToHostName(addrbin)   /* expand binary address to host name */
WRITE "binary IP address expands to ",hostname,!
SET ipaddr=$SYSTEM.INetInfo.HostNameToAddr(hostname)    /* host name to IP address */
WRITE "hostname corresponds to IP address ",ipaddr,!
```

8.4 IPv4 and IPv6

UDP supports both IPv4 and IPv6 Internet protocols. Because these protocols are incompatible, both the server and the client must use the same Internet protocol or the transmission will fail.

An IPv4 address has the following format. *n* is a decimal integer in the range 0 through 255:

```
n.n.n.n
```

You can specify the IPv4 protocol as "0.0.0.0".

An IPv6 address has the following full format. *h* is a hexadecimal number with four hexadecimal digits:

```
h:h:h:h:h:h:h:h
```

Commonly, IPv6 addresses are abbreviated by eliminating leading zeros and replacing consecutive sections of zeros with a double colon (::); only one double colon may be used in an IPv6 address. By using IPv4 abbreviation rules, you can specify the IPv6 protocol as ":::" (meaning that all eight *h* sections have the value 0000).

To establish the Internet protocol:

- The client must establish either IPv4 or IPv6 in the %New() method. The default is IPv4.
- This must match the IPv4 or IPv6 protocol specified in the **GetHostAddr()** method and supplied (in binary form) in the **Send()** method.

The following is an IPv4 transmission:

ObjectScript

```
Server
SET subj=##class(%Net.UDP).%New(3001,"127.0.0.1")

SET inmsg=sobj.Recv()
```

ObjectScript

```
Client
SET cobj=##class(%Net.UDP).%New() /* the default is IPv4 */
SET bhost=##class(%Net.UDP).GetHostAddr("127.0.0.1")
SET outmsg="this is the message to send"
WRITE cobj.Send(outmsg,bhost,3001)
```

The following is an IPv6 transmission:

ObjectScript

```
Server
SET x=##class(%SYSTEM.InetInfo).IsIPv6Enabled()
IF x=1 {
    SET subj=##class(%Net.UDP).%New(3001,"::1")

    SET inmsg=sobj.Recv() }
ELSE {WRITE "IPv6 not enabled" }
```

ObjectScript

```
Client
SET cobj=##class(%Net.UDP).%New(0,"::")
SET bhost=##class(%Net.UDP).GetHostAddr("::1")
SET outmsg="this is the message to send"
WRITE cobj.Send(outmsg,bhost,3001)
```

Methods for handling host addresses are found in the %SYSTEM.InetInfo class documentation. Further details on IPv4 and IPv6 formats can be found in [Use of IPv6 Addressing](#).

8.5 See Also

- [TCP Client/Server Communication](#)

- [TCP Advanced Topics](#)
- [Local Interprocess Communication \(Pipes\)](#)
- [Communication Between InterSystems IRIS Processes](#)
- [Use of IPv6 Addressing](#)

9

Terminal I/O

This page discusses terminal I/O in InterSystems IRIS® data platform.

9.1 Overview

ObjectScript provides commands that support serial asynchronous ASCII terminals. You can also use these commands with console I/O.

Using Terminal I/O, your routine can:

- Enable or disable the echo of incoming characters.
- Send and receive ANSI-standard escape sequences.
- Control keyboard interruptions and program special user interactions, including formatted screens, reverse video, and special keys for skipping fields.
- Enable and disable recognition of **Ctrl-C** interrupts.
- Control the flow of incoming and outgoing data by XON (**Ctrl-Q**) and XOFF (**Ctrl-S**).
- Specify COM port state parameters and modem baud rate.
- Conform to foreign protocols when you specify your own set of termination characters.
- Communicate with non-terminal devices, such as automated instruments.

Printers are handled as terminal I/O devices on most platforms. UNIX® systems always handle a printer as a terminal I/O device. On Windows, a printer connected through a serial communications port is handled as a terminal I/O device. Otherwise, Windows systems handle printers as sequential file I/O devices. For further details, see [Printers](#).

9.1.1 Your Login Terminal or Console is Your Principal Device

The terminal or console on which you log in to InterSystems IRIS is your principal device. You need not open your principal device. If you have not issued an **OPEN** and a **USE**, the first time a process issues a **READ** or **WRITE**, the system opens your principal device automatically, and establishes it as the current device, as if you had issued `OPEN 0 USE 0` explicitly.

Note: Through the rest of this page, the word *terminal* is used to refer to both terminals and consoles.

9.2 Special Variables Show I/O Conditions

I/O commands can affect the values of special variables. You can test these variables to determine I/O conditions:

- **\$IO** contains the name of the current device.
- **\$TEST** contains a boolean value that shows whether the most recent timed operation was successful.
- **\$X** and **\$Y** show the position of the cursor.
- **\$ZA**, **\$ZB**, and **\$KEY** show information about **READ** operations. **\$ZB** and **\$KEY** are similar, but not identical.

See [Introduction to I/O](#) for more information on the device-independent **\$IO** special variable. The next sections describe terminal-specific information about the remaining special variables.

9.2.1 \$X and \$Y and Cursor Position

\$X contains the horizontal position and **\$Y** the vertical position of the cursor or print head. $\$X=0$, $\$Y=0$ denotes the upper left corner of the CRT screen or the printed page. InterSystems IRIS calculates both **\$X** and **\$Y** modulo 256; that is, they range from 0 to 255 and then begin again at 0.

The following table shows the effects of writing or echoing the characters

Table 9–1: Effects of Echoing Characters

Character	ASCII Code	Effect on \$X	Effect on \$Y
Form Feed	12	$\$X=0$	$\$Y=0$
Return	13	$\$X=0$	$\$Y=\Y
Line Feed	10	$\$X=\X	$\$Y=\$Y+1$
Backspace	8	$\$X=\$X-1$	$\$Y=\Y
Tab	9	$\$X=\$X+1$	$\$Y=\Y
Any printable ASCII character	32 through 126	$\$X=\$X+1$	$\$Y=\Y

The **S** protocol of **OPEN** and **USE** turns off the echo. This protocol also disables the changing of **\$X** and **\$Y** during input, so that they truly indicate the cursor's position.

9.2.1.1 WRITE * and \$X and \$Y

WRITE * does not change **\$X** and **\$Y**. Thus, you can send a control sequence to your terminal and **\$X** and **\$Y** will still reflect the true cursor position. Some control sequences do move the cursor, so you can set **\$X** or **\$Y** directly when you need to.

9.2.1.2 \$X and \$Y Example

In the following example, a control sequence moves the cursor in a VT100 terminal to line 10, column 20, and sets **\$X** and **\$Y** accordingly.

ObjectScript

```

; set DY and DX to desired
; values for $Y and $X
SET DY=10
SET DX=20
; ...
; escape sequence moves
; cursor to desired position
WRITE *27, *91, DY+1, *59, DX+1, *72
; ...
; updates $X and $Y
SET $Y=DY
SET $X=DX

```

9.2.1.3 Effect of Escape Sequences on \$X and \$Y Varies

Escape sequences can alter the effect of echoing on the values of **\$X** and **\$Y**. Three factors control this effect:

- Your operating system, which sets the default behavior.
- Whether **/NOXY** (which disables **\$X** and **\$Y** processing) was specified in the **OPEN** or **USE** command.
- You can set how **\$X** handles escape sequences for the current process using the **DX()** method of the **%SYSTEM.Process** class. The system-wide default behavior can be established by setting the **DX** property of the **Config.Miscellaneous** class.

Escape Sequences Affect \$X and \$Y on Windows and UNIX® Systems

By default on UNIX® and Windows, when writing or echoing any string that includes the ASCII Escape character (decimal value 27), InterSystems IRIS updates **\$X** and **\$Y** just as it does for any other character sequence. Thus, ANSI standard control sequences, which the terminal acts on, but does not display, can upset the relationship of **\$X** and **\$Y** to the cursor's position.

The easiest way to avoid this problem is to use the **DX()** method to alter the behavior (see the next section). Alternatively, you can use the ASCII value of each character in the string in a **WRITE * statement**.

Control Sequence Example

Instead of using the code:

```
%SYS>WRITE $CHAR(27)_"[1m"
```

you can use the following equivalent statement that does not update **\$X** and **\$Y**:

```
%SYS>WRITE *27,*91,*49,*109
```

Switches Control Updates of \$X for Escape Sequences

To select non-default behavior for updating **\$X** for your process, issue the **DX(*n*)** method of the **%SYSTEM.Process** class.

The system manager can alter the system-wide default behavior by setting the **DX** property of the **Config.Miscellaneous** class.

In both cases, *n* has a value from 0 through 4, as follows:

Value	Default Behavior for Updating \$X
0	Default for InterSystems IRIS
1	DSM behavior
2	DTM/MSM behavior

For more information, see **\$X** in the *ObjectScript Language Reference*.

9.2.2 \$TEST Shows Timed Operation Results

The **\$TEST** special variable is set by commands that take a timeout value. These commands include **OPEN** and **READ**. The value of **\$TEST** can be set to 1 or 0:

- **\$TEST** is set to 1 if the timed command succeeded before the timeout expired.
- **\$TEST** is set to 0 if the timeout expires on a timed command.

Note: **OPEN** and **READ** commands without a timeout have no effect on **\$TEST**.

For more information, see **\$TEST** in the *ObjectScript Language Reference*.

9.2.3 \$ZA Shows READ Status

The **\$ZA** special variable contains a number of bit flags that show the status of the last **READ** on the current device. You cannot set **\$ZA**; InterSystems IRIS controls its value. **\$ZA** remains valid until the next **READ**. **\$ZA** contains the sum of the values listed in the table, which shows how your program can test this variable. (**\$ZA** also contains bit flags for modem connection status, which are not listed here. For a complete list of **\$ZA** bit flag values, see **\$ZA** in *ObjectScript Language Reference*.)

Table 9–2: \$ZA Read Status Values

Value	Test	Meaning
1	\$ZA#2	A Ctrl-C arrived, whether or not breaks were enabled.
2	\$ZA\2#2	The READ timed out.
256	\$ZA\256#2	InterSystems IRIS detected an invalid escape sequence.
512	\$ZA\512#2	The hardware detected a parity or framing error.

While many of the conditions that **\$ZA** shows are errors, they do not interrupt the program's flow by trapping to the **\$ZTRAP** special variable. Programs that are concerned with these errors must examine **\$ZA** after every **READ**. Of course, a **Ctrl-C** with breaks enabled will trap to **\$ZTRAP**. For more on error trapping and **\$ZTRAP**, see [Error Processing](#) and [\\$ZTRAP](#) in the *ObjectScript Language Reference*.

9.2.4 \$ZB Shows What Ended a READ

\$ZB shows what character sequence or event ended the last **READ** operation on the current device. You cannot set **\$ZB**; InterSystems IRIS sets the value of **\$ZB** each time you perform a **READ**. You can use this value to act on non-printable characters such as the up arrow key or function keys.

\$ZB can contain any of the following:

- A termination character, such as a carriage return
- An escape sequence
- Character number *y* of a fixed-length **READ** `x#y`
- The single character of **READ** `*x`
- An empty string after a timed **READ** expires

\$ZB never contains more than 64 characters. A longer escape sequence is invalid.

9.2.4.1 \$ZB Example

The following example assigns the user-specified input characters to the **READ** command variable *x*, and assigns the input terminator (usually the Return character) to the **\$ZB** special variable. When issuing this command from the terminal prompt, you need to set a variable to trap the value of **\$ZB** on the same command line as the **READ** command. This is because the line return used to issue a command line is written to **\$ZB** as a terminator character. This example uses **ZZDUMP** to display the value of the characters trapped by **\$ZB**.

```
USER>READ x SET y=$ZB
USER>ZZDUMP y

0000: 0D
USER>
```

9.3 OPEN and USE Commands

9.3.1 OPEN Command

Establishes ownership of the terminal. An optional parameter list can set the right margin, specify device protocols, and specify one or more termination characters. Following the parameter list, you can optionally specify a *timeout* argument, and/or a *mnespace* argument. The *mnespace* argument specifies the InterSystems IRIS routine where control mnemonics for use with **WRITE** /*mnemonic* are defined.

OPEN pauses the process until the system finishes opening the device. If you press **Ctrl-C** to interrupt the **OPEN** command, a <NOTOPEN> error results.

OPEN retains control until the opening of the device is complete, unless you specify a timeout. With a timeout, if InterSystems IRIS cannot open the device in the number of seconds you specify, it sets **\$TEST** to 0 and returns control to the process. Even if a device is unavailable at the operating-system level, **OPEN** keeps trying to obtain the device until it succeeds or the timeout expires.

9.3.1.1 OPEN Syntax

The **OPEN** command takes the following arguments:

```
OPEN terminal:(margin:protocols:terminator:portstate:baud):timeout:"mnespace"
```

Only the *terminal* argument is required. The *terminal* argument can be an expression whose value is the name of a terminal device. Zero (0) is the process's principal device. **\$IO** is the current device. The maximum length of *terminal* is 256 characters.

Arguments are separated by colons (:). If you omit an argument within the list, you must specify the colon as placeholder. However, trailing colons are not permitted; you must not end either the command or its parameter list with a colon.

The optional parameter list is enclosed in parentheses and can contain the following optional parameters:

- *margin* is an integer that specifies the number of characters per line by specifying the right margin.
- *protocols* is one or more letter codes that specify terminal options.
- *terminator* is a string of one or more characters that terminate a **READ** operation. These characters supplement the termination characters that are defined for a specific *protocols*.
- *portstate* is a string that specifies the COM port state.
- *baud* is an integer that specifies the baud rate for a COM port.

You can specify these optional parameters as either [positional parameters](#) (in the order shown), or as [keyword parameters](#) with the syntax `/KEYWORD=value`. Keyword parameters may be specified in any order; because InterSystems IRIS executes parameters in left-to-right order, interactions between parameters may dictate a preferred order in some cases. You can mix positional parameters and keyword parameters in the same parameter list. The enclosing parentheses are required if you specify more than one parameter.

The following parameter lists are equivalent:

ObjectScript

```
OPEN $IO:(80:"BFU":$CHAR(13))
; all positional
OPEN $IO:(80::$CHAR(13):/PARAMS="BFU")
; mixed positional and keyword, using the /PARAMS keyword
; to specify a protocol letter code string.
OPEN $IO:(/MARGIN=80:/TERMINATOR=$CHAR(13):/BREAK:/FLUSH:/UPCASE)
; all keyword, using separate keywords
; for each protocol letter code.
```

Following the parameter list (or a placeholder colon, if no parameter list is specified), you can specify an optional *timeout* in seconds, and a *mnespace* argument to specify the routine that contains the control mnemonics for this device.

For more information, see [OPEN](#) in the *ObjectScript Language Reference*.

9.3.2 USE Command

Makes the specified terminal the current device. In programmer mode, all subsequent I/O commands on the same line of code refer to that device. In application mode, the device you name in a **USE** command remains the current device until the next **USE** command.

9.3.2.1 USE Syntax

The **USE** command takes the following arguments:

```
USE terminal:(margin:protocols:terminator):"mnespace"
```

The *terminal* argument can be an expression whose value is the name of a terminal device. Zero (0) is the process's principal device. **\$IO** is the current device. The maximum length of *terminal* is 256 characters.

Arguments are separated by colons (:). If you omit an argument, you must specify the colon. You must not end either the command or its parameter list with a colon.

The optional parameter list is enclosed in parentheses and can contain the *margin*, *protocols*, and *terminator* parameters. You can specify the optional *margin*, *protocols*, and *terminator* parameters as either [positional parameters](#) (in the order shown), or as [keyword parameters](#) with the syntax `/KEYWORD=value`. Keyword parameters may be specified in any order; because InterSystems IRIS executes parameters in left-to-right order, interactions between parameters may dictate a preferred order in some cases. You can mix positional parameters and keyword parameters in the same parameter list. The enclosing parentheses are required if you specify more than one parameter.

To specify COM port state and baud rate with the **USE** command, use the appropriate [keyword parameters](#).

Following the parameter list (or a placeholder colon, if no parameter list is specified), you can specify an optional *mnespace* argument, which identifies an ObjectScript routine where control mnemonics for use with `WRITE /mnemonic` are defined.

For more information, see [USE](#) in the *ObjectScript Language Reference*.

9.3.3 Positional Parameters for OPEN and USE Commands

The following positional parameters are available for the **OPEN** and **USE** commands. You can set these parameters for a device in either the **OPEN** or **USE** command, or take the defaults configured in the Management Portal. These parameters are positional; if you omit a parameter, you must include its preceding colon as a placeholder.

9.3.3.1 margin

The 1st positional parameter: An integer value specifying the right margin (and thus the number of characters per line). Values from 1 to 255 set the right margin for output; any other value disables the right margin. An empty string leaves the margin setting unchanged. On Windows platforms, you cannot use “:n” to control the print margin used. Such notation is ignored by InterSystems IRIS. Code such as “|PRN|:121” is ignored. To control the printer width, send the appropriate control characters for that printer. The notation does work on other platforms.

The default margins for various terminal types are defined in the Management Portal. Select **System Administration, Configuration, Device Settings, Device Subtypes**. When you click on “Edit” for each listed device subtype, it displays a **Right Margin**: default option.

9.3.3.2 protocols

The 2nd positional parameter: A string of letter code characters enclosed in quotation marks (for example, "BNFU"), where each letter enables one of the terminal's rules for communicating. Letter codes are not case-sensitive. Letter codes may be specified in any order; because InterSystems IRIS executes them in left-to-right order, interactions between letter codes may dictate a preferred order in some cases. For a table of letter codes, see [Letter Code Protocols](#).

A preceding plus or minus affects protocols as follows:

- No preceding plus or minus: New string replaces prior protocols string.
- Plus (+) precedes letter code string: Protocols in new string are added to prior protocols string.
- Minus (-) precedes letter code string: Protocols in new string are turned off, but other protocols remain in effect.

The + and – options for turning protocols on and off are not available in DSM-11 compatibility modes.

9.3.3.3 terminator

The 3rd positional parameter: A string of up to eight characters, any of which will terminate a **READ**. These terminators are in addition to those built into the protocols. See [Using Terminators to End I/O Operations](#).

9.3.3.4 portstate

The 4th positional parameter: A string of up to eight bytes in positional order that govern the COM port state. The portstate bytes are as follows (bytes are numbered from 1 in left-to-right order):

Byte	Meaning	Values
1	Disconnect	D=disconnect (hangup) the port. blank=do not disconnect the port.
2	Modem Control	1=use modem control. 0=do not use modem control. blank=no change to modem control.
3	Data Bits	5=five data bits. 6=six data bits. 7=seven data bits. 8=eight data bits. blank=no change to data bit setting.
4	Parity	0=no parity. 1=odd parity. 2=even parity. 3=mark parity. 4=space parity. blank=no change to parity setting.

Byte	Meaning	Values
5	Stop Bits	1=one stop bit. 5=1.5 stop bits. 2=two stop bits. blank=no change to stop bit setting.
6	Flow Control	X=use Xon/Xoff flow control. C=use CTS/RTS flow control. D=use DSR/DTR flow control. N=disable flow control. blank=no change to flow control.
7	DTR Setting	0=disable DTR (set it off, keep it off). 1=enable DTR (set it on, keep it on). blank=no change to DTR state.
8	\$ZA Error Reporting	0=disable \$ZA error reporting (default). 1=enable \$ZA error reporting. blank=no change to \$ZA error reporting.

The following example shows a COM port state string:

ObjectScript

```
OPEN "COM2" : ( : : : " 0801x0" )
```

The string values are: blank (do not disconnect the port); 0 (do not use modem control); 8 (eight data bits); 0 (no parity); 1 (one stop bit); X (use Xon/Xoff flow control); 0 (disable DTR); default (disable \$ZA error reporting).

The *Disconnect* parameter performs a hangup on modem-controlled ports by lowering the DTR signal for two seconds and then restoring it. A disconnect does not close the port; following a disconnect you can dial out again without reopening the COM device.

The *Modem Control* parameter determines how InterSystems IRIS responds to the state of the RLSD (Received Line Signal Detector) pin, also known as the DCD (Data Carrier Detect). If the line is modem controlled (modem control=1), InterSystems IRIS monitors the state of the RLSD, and generates an <ENDOFFILE> error if a **READ** command is issued when carrier is not present. InterSystems IRIS does not generate an error when a **WRITE** command is issued when carrier is not present. This is because it must be possible to send the dial command to the modem prior to a connection being established. InterSystems IRIS modem control can be enabled (1) or disabled (0) at any time. It is suggested that you disable modem control while sending commands to the modem, then enable modem control once carrier is detected and connection has been established.

The *DTR Setting* parameter is used to control login from an attached modem. If the DTR setting is 0 (zero), the DTR control signal is off, and modems cannot communicate with the computer. This prevents a dial-in connection from occurring. If the DTR setting is 1 (one), the DTR control signal is on, and modems can communicate with the computer. A dial-in connection can occur. If you configure DTR as off (0), then you must set it to on (1) with the **OPEN** command or **USE** command to be able to dial out using a connected modem. In most cases, the DTR setting is unimportant when using a null modem cable to connect directly to a terminal device or a serial printer. This is because the null modem cable should force the DTR control pin on.

The *\$ZA Error Reporting* parameter enables reporting of the status of modem control pins to the **\$ZA** special variable. This checking can be done regardless of the Modem Control byte setting for the COM port. If \$ZA error reporting is enabled, COM port errors are cleared with a call to the Windows ClearCommError() function. The port error state is reported in the **\$ZA** bits 16 through 22. For a table of **\$ZA** bit values, refer to **\$ZA** in the *ObjectScript Reference*.

9.3.3.5 baud

The 5th positional parameter: an integer value that specifies the desired COM port baud rate. The following baud rates are supported: 110, 300, 600, 1200, 4800, 9600, 14400, 19200, 38400, 56000, 57600, 115200, 128000, 256000.

9.3.4 Keyword Parameters for OPEN and USE Commands

The following table describes the keyword parameters for controlling terminal devices with both **OPEN** and **USE** commands. For each keyword, the table lists the corresponding [Letter Code Protocols](#) for **OPEN** and **USE**. Additional information on the use of these protocols can be found in the Letter Code Protocols table.

Table 9–3: OPEN and USE Keyword Parameters for Terminal Devices

Keyword	Default	Letter Code Protocols	Description
/BAUD= <i>n</i>			Corresponds to the <i>baud</i> positional parameter. /BAUD= <i>n</i> sets the modem baud rate for a port. Supported values depend on the operating system support. /SPEED is an alias for /BAUD.
/BREAK[= <i>n</i>] or /BRE[= <i>n</i>]	0	B	/BREAK or /BREAK= <i>n</i> for nonzero values of <i>n</i> enable the protocol. /BREAK= <i>n</i> for a zero value of <i>n</i> disables the protocol.
/COMPARAMS= <i>str</i>			Corresponds to the <i>portstate</i> positional parameter. (This keyword provides a way to specify a COM port state byte code string in a position-independent way.) The <i>portstate</i> byte codes that you can include in <i>str</i> , are listed in a table in earlier on this page.
/COMPRESS= <i>str</i>	""		Specifies the stream data compression type. You can enable a compression type of ZLIB or ZSTD. You can specify /COMPRESS="" to disable compression. /COMPRESS="zlib" is equivalent to /GZIP=1. To compress a string, use %SYSTEM.Util.Compress().
/CRT[= <i>n</i>]	Depends on the operating system terminal setting	C and P	Associated with the C and P protocols. /CRT or /CRT= <i>n</i> for nonzero values of <i>n</i> enable the C protocol and disable the P protocol. /CRT= <i>n</i> for a zero value of <i>n</i> disables the C protocol and enables the P protocol.
/DATABITS= <i>n</i>			Sets the number of data bits for a serial port. Valid values are 5, 6, 7, or 8.
/DISCONNECT			Corresponds to 1st byte of the <i>portstate</i> positional parameter. /DISCONNECT disconnects (hangs up) the COM port. It does not close the port; you can dial out again without reopening the COM device.

Keyword	Default	Letter Code Protocols	Description
/ECHO[= <i>n</i>]	1	S	/ECHO or /ECHO= <i>n</i> for nonzero values of <i>n</i> disable the protocol. /ECHO= <i>n</i> for a zero value of <i>n</i> enables the protocol.
/EDIT[= <i>n</i>]	0	R and N	/EDIT or /EDIT= <i>n</i> for nonzero values of <i>n</i> enable the R protocol and disable the N protocol. /EDIT= <i>n</i> for a zero value of <i>n</i> disables the R protocol and enables the N protocol.
/FLOW= <i>str</i>			Specifies the type of flow control to use for a serial port. Valid values are NONE and XON. Some operating systems also support RTSCTS.
/FLUSH[= <i>n</i>] or /FLU[= <i>n</i>]	0	F	/FLUSH or /FLUSH= <i>n</i> for nonzero values of <i>n</i> enable the protocol. /FLUSH= <i>n</i> for a zero value of <i>n</i> disables the protocol.
/GZIP[= <i>n</i>]	1		Specifies GZIP-compatible stream data compression. /GZIP or /GZIP= <i>n</i> (for nonzero values of <i>n</i>) enables compression on WRITE and decompression on READ. /GZIP=0 disables compression and decompression. Before issuing /GZIP=0 to disable compression and decompression, check the \$ZEOS special variable to make sure that a stream data read is not in progress. /GZIP compression has no effect on I/O translation, such as translation established using /IOTABLE. This is because compression is applied after all other translation (except encryption) and decompression is applied before all other translation (except encryption).
/IMAGE[= <i>n</i>] or /IMA[= <i>n</i>]	0	I	/IMAGE or /IMAGE= <i>n</i> for nonzero values of <i>n</i> enable the protocol. /IMAGE= <i>n</i> for a zero value of <i>n</i> disables the protocol.
/IOTABLE[= <i>name</i>] or /IOT[= <i>name</i>]	If <i>name</i> is not specified, the default I/O translation table for the device is used.		Corresponds to the K\name\ protocol, which establishes an I/O translation table for the device.

Keyword	Default	Letter Code Protocols	Description
/MARGIN= <i>n</i> or /MAR= <i>n</i>	0 (no margin)		Corresponds to the <i>margin</i> positional parameter, which sets the right margin for the terminal device.
/MODE= <i>n</i>	No default		Resets protocols and sets the terminal mode according to the value of <i>n</i> . <i>n</i> =0 sets LF and ESC as default terminators. <i>n</i> =1 is the same as mode 0 and enables the S protocol. <i>n</i> =2 is the same as mode 0 and enables the T protocol.
/NOXY [= <i>n</i>]	0		No \$X and \$Y processing: /NOXY or /NOXY= <i>n</i> (for nonzero values of <i>n</i>) disables \$X and \$Y processing. This can substantially improve performance of READ and WRITE operations. The values of the \$X and \$Y variables are indeterminate, and margin processing (which depends on \$X) is disabled. /NOXY=0 enables \$X and \$Y processing; this is the default.
/OBUFSIZE= <i>nnn</i>	256		Specifies the size of the terminal output buffer in bytes. Increasing the output buffer size can improve performance of screen painting with telnet over wide area networks with high latency. Valid values for /OBUFSIZE are 256 through 65536. The default is 256.
/PARAMS= <i>str</i> or /PAR= <i>str</i>	No default		Corresponds to the <i>protocols</i> positional parameter. (This keyword provides a way to specify a protocols letter code string in a position-independent way.) For a table of letter codes that you can include in <i>str</i> , see Letter Code Protocols .
/PARITY= <i>str</i>			Specifies the type of parity checking for a serial port. Valid values are NONE, EVEN, ODD. Some operating systems also support MARK and SPACE.
/SPEED= <i>n</i>			/SPEED is an alias for /BAUD.
/STOPBITS= <i>n</i>			Sets the number of stop bits for a serial port. Valid values are 1 or 2.

Keyword	Default	Letter Code Protocols	Description
<code>/TERMINATOR=<i>str</i></code> <i>or</i> <code>/TER=<i>str</i></code>	No default		Corresponds to the <i>terminator</i> positional parameter, which establishes user-defined terminators. To compose <i>str</i> , see Using Terminators to End I/O Operations .
<code>/TPROTOCOL[=<i>n</i>]</code> <i>or</i> <code>/TPR[=<i>n</i>]</code>	0	T	<code>/TPROTOCOL</code> or <code>/TPROTOCOL=<i>n</i></code> for nonzero values of <i>n</i> enable the protocol. <code>/TPROTOCOL=<i>n</i></code> for a zero value of <i>n</i> disables the protocol.
<code>/TRANSLATE[=<i>n</i>]</code> <i>or</i> <code>/TRA[=<i>n</i>]</code>	1	K	<code>/TRANSLATE</code> or <code>/TRANSLATE=<i>n</i></code> for nonzero values of <i>n</i> enable I/O translation for the device. <code>/TRANSLATE=<i>n</i></code> for a zero value of <i>n</i> disables I/O translation for the device.
<code>/UPCASE[=<i>n</i>]</code> <i>or</i> <code>/UPC[=<i>n</i>]</code>	0	U	<code>/UPCASE</code> or <code>/UPCASE=<i>n</i></code> for nonzero values of <i>n</i> enable the protocol. <code>/UPCASE=<i>n</i></code> for a zero value of <i>n</i> disables the protocol.
<code>/XYTABLE[=<i>name</i>]</code> <i>or</i> <code>/XYT[=<i>name</i>]</code>	If <i>name</i> is not specified, the default <code>\$X/\$Y</code> action table for the device is used.	<code>Y\name\</code>	Corresponds to the <code>Y\name\</code> protocol, which establishes a <code>\$X/\$Y</code> action table for the device.

9.3.5 Testing the Success of OPEN Commands

To determine whether an **OPEN** command succeeded, your code should test **\$TEST** and/or **\$ZE**. **\$TEST** is only set if the **OPEN** command was specified with a *timeout* argument. A `<NOTOPEN>` error occurs only when **Ctrl-C** interrupts an **OPEN** command. Therefore, your code must not depend on `<NOTOPEN>` errors.

9.3.6 Letter Code Protocols for OPEN and USE

Special situations or terminals can require different protocols. With the *protocols* letter code parameter (or the corresponding keyword parameters) you can change the rules by which InterSystems IRIS communicates with the terminal. Protocols affect normal and single-character reads alike.

Normal mode, with all special protocols disabled, suffices for most terminal I/O. In normal mode InterSystems IRIS echoes each incoming ASCII character, sending it back to appear on the terminal. A **Return**, or a valid escape sequence, ends a **READ** command.

Issuing **OPEN** for a terminal turns off all previous protocols, except when you use the `+` and `-` options.

The following table describes valid *protocols* characters and their effects.

Table 9–4: Letter Code Protocols for OPEN and USE

Protocol Character	Name	Definition
B	BREAK	<p>If breaks are enabled (+B), Ctrl-C interrupts a running routine with an <INTERRUPT> error. If breaks are disabled (-B), Ctrl-C does not cause an interrupt and “^C” is not displayed. The use of this protocol is dependent upon the BREAK command default established by the login mode, as follows:</p> <p>If you log in as programmer mode, interrupts are always enabled (BREAK 1). The B (or /BREAK) protocol specified in an OPEN or USE command has no effect.</p> <p>If you log in as application mode, BREAK 0 is the default, and interrupts can be enabled or disabled by the B (or /BREAK) protocol specified in the OPEN or USE command.</p>
C	CRT terminal	<p>C mode accepts all eight bit characters as data, except for the following six: ASCII 3, 8, 10, 13, 21, and 127. The ASCII 127 Delete character echoes as a destructive backspace, that is, it backspaces and erases the preceding character. ASCII 21 (Ctrl-U) echoes enough destructive backspaces to bring the cursor to the start of the READ. If the setting for the right margin, or the nature of the terminal, forces echoed characters to begin a new line, Ctrl-U can erase only the characters on the last physical line. In any case, Ctrl-U cancels all input since the start of the READ. C is mutually exclusive with the P protocol.</p>
F	Flush	<p>Flush (empty) the input buffer before each READ. You can flush the input buffer to prohibit the user from typing ahead of READ operations on the terminal, because InterSystems IRIS discards anything typed between READ operations. Note that the command <code>WRITE *-1</code> flushes the input buffer at any time, regardless of the F protocol.</p>
I	Image mode	<p>I mode accepts all 256 eight bit characters as data, treating none as a READ terminator, except the termination character(s) (if any) that you explicitly specify in the <i>terminator</i> parameter. If you do not explicitly specify termination characters, you should use only single character and fixed length READ operations. Without defined termination characters, an ordinary READ results in a <TERMINATOR> error.</p> <p>Image mode (I) <i>protocol</i> can be combined with other <i>protocol</i> characters. In image mode, InterSystems IRIS ignores the protocol characters P, C and B. In image mode, the protocol characters F, N, R, S, and T remain in effect. When not in image mode, the device is in N (normal) mode.</p>

Protocol Character	Name	Definition
K\name\ or Knum	I/O Translation Mode	When you use the K protocol for a device, I/O translation will occur for that device if translation has been enabled system-wide. You identify the previously defined table on which the translation is based by specifying the table's name. (The older form Knum, where "num" represents the number of the slot the table is loaded in, is being phased out but is still supported.)
N	Normal mode	N mode accepts all eight bit characters as data, except for the following six: ASCII 3, 8, 10, 13, 21, and 127. These implicit terminator and command line editing control characters, are described later on this page. If R (read line recall) protocol is enabled, N disables R protocol. This mode is the default if no <i>protocols</i> value is specified.
P	Print device	The ASCII Delete character echoes as a backslash (\), and Ctrl-U echoes as "^U" followed by a carriage return and line feed. When you issue an OPEN command for a terminal, InterSystems IRIS invokes the protocol C or P automatically, depending on the operating system terminal setting. These protocols remain in effect until you change the protocols for the device explicitly. A protocol string containing neither C nor P does not cancel this protocol.
R	Enable read line recall mode	The R protocol enables read line recall mode for that device. To activate read line recall for the current process, use the LineRecall() method of the %SYSTEM.Process class. To set the system-wide read line recall default, use the <i>LineRecall</i> property of the Config.Miscellaneous class. The R protocol overrides these default settings for the specified device. To change read line recall for an already-open device, you must explicitly specify another OPEN command to that device. Read line recall is disabled by specifying the N protocol.
S	Secret input	Nothing echoes on a READ . READ commands do not change \$X and \$Y . Read line recall is disabled.
T	Terminator	T mode does not treat any control characters as data. The following are control characters: ASCII characters with decimal values from 0 to 31 and 127 to 159. Most of these control characters are treated as READ terminator characters. The exceptions are the following control characters, which perform other control operations: ASCII 3 (Ctrl-C), ASCII 8 (backspace), ASCII 17 (Ctrl-Q), ASCII 19 (Ctrl-S), ASCII 21 (Ctrl-U), ASCII 24 (Ctrl-X), ASCII 27 (ESC), and ASCII 127 (DEL). When T mode is combined with I mode (IT protocol) all control characters (ASCII 0 to 31 and 127 to 159) are treated as READ terminator characters, with the exceptions of the output control characters Ctrl-Q (XOFF), and Ctrl-S (XON), and the input control characters Ctrl-H and Ctrl-Y . Output control characters Ctrl-Q and Ctrl-S are intercepted by most terminals and do not terminate a READ even in IT mode.
U	Uppcase mode	U mode converts all input letters to upper case.

Protocol Character	Name	Definition
Y{name\ or Ynum	\$X/\$Y Action Mode	When you use the Y protocol for a device, the system uses the named \$X/\$Y Action Table. You identify a previously defined \$X/\$Y Action Table on used to translate by specifying the table name. \$X/\$Y action is always enabled. If Y is not specified and a system default \$X/\$Y is not defined, a built in \$X/\$Y action table is used. The + option works for turning on the Y protocol, but the - option does not. In order to disable a \$X/\$Y association, you can issue the command: <code>USE 0 : (: "Y0 ")</code> (The older form Ynum, where <i>num</i> represents the number of the slot the table is loaded in, is being phased out but is still supported.)

9.3.6.1 Examples of Protocol Strings

The following series of examples show how protocol strings function. Each of the following USE commands builds on the protocol established by the preceding USE commands:

ObjectScript

```
USE 0 : ( 80 : "BP" )
```

The letter codes BP turn on the B and P protocols. This example enables breaks (B) and tells InterSystems IRIS to treat the terminal as a printing device (P).

ObjectScript

```
USE 0 : ( 80 : "P" )
```

When it follows the USE command in the example just above, this command leaves the P protocol in effect, but turns off the B protocol.

ObjectScript

```
USE 0 : ( 80 : "+R" )
```

+R turns on read line recall, without affecting other protocol settings.

ObjectScript

```
USE 0 : ( 80 : "" )
```

The empty string turns off all protocols. However, the P or C protocol remains in effect.

ObjectScript

```
USE 0 : ( 80 )
```

Omitting the protocol parameter leaves the protocol and explicit terminators unchanged.

9.3.7 Protocol Terminator Characters

OPEN and USE protocols define what READ input characters, control sequences, and keystrokes are treated as implicit terminator characters. These four protocols are I (image mode), N (normal mode (the default)), R (read line recall mode), and T (terminator mode):

- I (image mode) accepts all 256 eight bit characters as data, treating none as a READ input terminator or a command line editing character. Because of this, you should use only single character or fixed length **READ** operations in image mode. Without defined termination characters, an ordinary **READ** results in a <TERMINATOR> error.
- N (normal mode) and C (CRT mode) accept all characters as data except the following six: ASCII 3, 8, 10, 13, 21, and 127. Two of these, ASCII 10 (linefeed) and 13 (carriage return) terminate READ and submit input. ASCII 3 (**Ctrl-C**) discards input and issues an <INTERRUPT> error if **BREAK** is enabled. ASCII 8 (backspace) and 127 (delete) perform a single-character backspace erase then continue READ. ASCII 21 performs a multi-character backspace, erasing all prior characters, then continues READ.
- R (read line recall mode) accepts all characters as data except the following twenty: ASCII 1 through 8, 10 through 14, 16, 18, 21, 23, 24, 27, and 127. ASCII 10 (linefeed) and 13 (carriage return) terminate READ and submit input. ASCII 3 (**Ctrl-C**) discards input and issues an <INTERRUPT> if **BREAK** is enabled. The other characters perform the following command line editing functions:
 - 1 ^A = beginning of line
 - 2 ^B = back word
 - 3 ^C = interrupt
 - 4 ^D = delete current character
 - 5 ^E = end of line
 - 6 ^F = forward word
 - 7 ^G = delete to beginning of word ("wipe word backward")
 - 8 ^H = BS = destructive backspace
 - 9 ^I = HT = horizontal tab (echoed as a SPACE)
 - 10 ^J = LF = end of input
 - 11 ^K = VT = forward character
 - 12 ^L = FF = erase to end of line
 - 13 ^M = CR = end of input (same as LF)
 - 14 ^N = recall next input line
 - 16 ^P = recall previous input line
 - 18 ^R = back char (reverse)
 - 21 ^U = erase to start of line
 - 23 ^W = delete to end of word "gobble word forward"
 - 24 ^X = erase entire line
 - 27 ESC lead character for arrow and function keys
 - 127 DEL = destructive backspace (same as BS)
- T (terminator mode) accepts all characters as data except the 65 control characters: ASCII 0 through 31 and ASCII 127 through 159. Most of these characters are treated as READ termination characters. This includes the tab character (ASCII 9), which is treated as a data character in all other protocols. A few characters are treated as command line control characters: ASCII 3 (**Ctrl-C**) discards input and issues an <INTERRUPT> if **BREAK** is enabled. ASCII 8 (backspace) and 127 (delete) perform a single-character backspace erase then continue READ. ASCII 21 (**Ctrl-U**) and ASCII 24 (**Ctrl-X**) perform a multi-character backspace, erasing all prior characters, then continues READ. ASCII 27 is the Escape character.
- IT (image mode + terminator mode) accepts all characters as data except the 65 control characters: ASCII 0 through 31 and ASCII 127 through 159. It treats all of the control characters as READ terminator characters.

In any of these modes you can explicitly specify additional terminator characters using the *terminator* parameter. Because image mode is commonly used for bit stream data, designation of any character as a terminator is usually avoided.

9.3.8 Explicit Terminator Characters

The *terminator* parameter in the **OPEN** or **USE** command lets you define specific characters as terminators for a **READ** or **WRITE** command. These explicit terminators can be used to supplement the terminator characters supplied by the specified *protocol*. The *terminator* parameter can also be used to override the designation of a character by the *protocol*, and instead designate it a terminator character. The exceptions to this ability to redefine a character as a terminator are: ASCII 0 (NULL), ASCII 3 (**Ctrl-C**), and the two output control characters **Ctrl-Q** (XON) and **Ctrl-S** (XOFF). These retain their functionality, and cannot be redefined as terminator characters.

9.3.8.1 Example

This example defines **Z**, **Backspace** and **Tab** as terminators for the principal device. The underscore is the concatenate operator.

ObjectScript

```
USE 0: ("": "" : "Z"_$CHAR(8,9))
```

By issuing an **OPEN** command for an unowned terminal, you implicitly clear the InterSystems IRIS internal list of explicit terminators. When a protocol string appears, InterSystems IRIS then does the following:

1. Clears its list of explicit terminators.
2. Sets protocols according to the protocol string.
3. Copies a terminator string, if any, into the internal list of explicit terminators.

The following table gives examples of explicit terminator strings.

Table 9–5: Terminator Strings: Examples

Terminator String	Definition
USE 0:(80:"C":\$CHAR(27))	The Escape character terminates a READ rather than beginning an escape sequence.
USE 0:(80:"C": "")	The empty string clears all terminators.
USE 0:(80:"C")	Omitting the <i>terminator</i> parameter when you specify <i>protocol</i> clears all terminators.
USE 0:(80) or U 0:80	Omitting both <i>protocol</i> and <i>terminator</i> leaves terminators unchanged.

9.3.9 Summary of Protocols and Terminators in Read Operations

The following characters end a normal (nonimage) mode **READ**:

- **Enter**
- Any character in the terminator string except ASCII NUL and the characters **Ctrl-C**, **Ctrl-O**, **Ctrl-Q**, and **Ctrl-S**.
- With the T protocol in effect, any control character except the output control characters. Control characters are non-printing characters with decimal values 0 to 31 and 127 to 159.
- Any escape sequence.
- Character number *y* of a fixed-length **READ** *x#y*.

The following characters end an image-mode **READ**:

- Any character specified in the terminator string except ASCII NUL.
- With the T protocol in effect, any control character.
- Character number *y* of a fixed-length **READ** *x#y*.

9.4 READ Command

Reads from 0 to 32 KB from the keyboard into the named variable. The *timeout* argument is optional. The command cannot end with a pound sign (#) or colon (:)

9.4.1 Syntax

```
READ variable:timeout ; Variable-length read
READ variable#length:timeout ; Fixed-length read
READ *variable:timeout ; Single-character read
```

For more information, see [READ](#) in the *ObjectScript Language Reference*.

9.4.2 Examples

The following table gives several examples of how you use these arguments.

Table 9–6: READ Command Arguments: Examples

Example	Effect
READ ^GLO	Reads characters from the current device until it finds a terminator, and puts the resulting string in the global ^GLO.
READ X:60	Reads from the current device until it finds a terminator, and puts the string read into the variable X. Waits up to 60 seconds for the input to end before timing out. Striking a key does not reset the timeout value.
READ *X	Reads a single character from the current device and puts its decimal value in the local variable X.
READ X#1	Reads a single character from the current device and puts its string value into the local variable X.
READ X#45:60	Reads up to 45 characters from the current device and puts the string value into the local variable X. Waits up to 60 seconds for the input to end before timing out.

9.4.3 Read Line Recall

Read line recall mode provides line recall of editable lines as input for **READ** operations from a terminal. These recallable lines include both previous **READ** input lines and previous command lines. Echoing of input lines is a necessary precondition for read line recall.

InterSystems IRIS supports read line recall for both variable-length terminal reads (`READ variable`) and fixed-length terminal reads (`READ variable#length`). InterSystems IRIS does not support read line recall for single-character terminal reads (`READ *variable`). Read line recall supports the optional *timeout* argument.

For a fixed-length terminal read, the recalled line is truncated to one character less than the number of characters specified in the **READ**. This final **READ** character position is reserved for typing a line termination character, specifying an edit character, or adding one more data character.

When read line recall is active, you can provide input to a **READ** by using the **Up Arrow** and **Down Arrow** keys to recall a previous terminal input line. You can then use the **Left Arrow**, **Right Arrow**, **Home**, and **End** keys to position the cursor for editing the recalled line. You can use the **Backspace** key to delete a character, **Ctrl-X** to delete the entire line, or **Ctrl-U** to delete all of the line to the left of the cursor.

When read line recall is not active, the four **Arrow** keys, the **Home** key, and the **End** key all issue a line termination character. You can use the **Backspace** key to delete a single input character, and **Ctrl-X** (or **Ctrl-U**) to delete the entire input line.

You can use the **OPEN** or **USE** command to activate read line recall by specifying the R protocol, or to deactivate read line recall by specifying the N, I, S, or T protocol.

9.4.4 Special Protocol Characters Affect Terminal I/O

Each operating system intercepts certain protocol characters (UNIX®) or key combinations (such as **CTR-ALT-DEL** on Windows platforms), preventing these characters from affecting InterSystems IRIS. The console for Windows makes no attempt to override these operating system characteristics.

Other special characters can alter the way your routines execute, but do not appear in the **READ** command variable. Operating your terminal in image mode cancels these effects and causes InterSystems IRIS to treat these characters like any others.

READ is affected by output and input control characters. **READ** simply reads all other control characters, except termination characters. It does not echo them.

Output control characters affect both the flow and the output of a routine. These are described in the following table:

Table 9–7: Output Control Characters

Output Control Character	Decimal Value	Definition
Ctrl-C	3	If breaks are enabled, Ctrl-C interrupts a routine's execution. The routine behaves as though an <INTERRUPT> error has occurred. If breaks are disabled, Ctrl-C causes InterSystems IRIS to discard anything entered thus far in the current READ . You can use Ctrl-C to interrupt global module requests that require network operations. To trap Ctrl-C , set the special variable \$ZTRAP . For additional information, see the section on enabling breaks.
Ctrl-S	19	Ctrl-S suspends output to the terminal. Output to the terminal resumes when InterSystems IRIS encounters a Ctrl-Q .
Ctrl-Q	17	Ctrl-Q resumes output suspended by Ctrl-S .

Input control characters affect input. Image mode (I protocol) treats these characters as data, but in normal mode they affect input to the current **READ** command. These characters are described in the following table:

Table 9–8: Input Control Characters

Input Control Character	Decimal Values	Definition
Delete	127	The Delete character removes the last character entered. If you press Delete repeatedly, you remove characters from right to left, but not beyond the beginning of the current READ . Delete uses a backspace to erase the last character on a CRT screen. Delete echoes as a backslash character ("\") on a printing terminal (such as a teletype).
Ctrl-U	21	Deletes either all characters you have entered since the start of the current READ or the contents of the UNIX® type-ahead buffer until the last carriage return. Ctrl-U erases the deleted characters on a CRT; on a printer it echoes ^U and sends a Return and LineFeed To flush the typeahead buffer completely, use Ctrl-X .

Input Control Character	Decimal Values	Definition
Ctrl-H	8	Performs the same function as Delete on some systems.
Return	13	A carriage return ends a READ in all protocols except "I" (image mode).
Escape	27	Begins an escape sequence. The sequence itself ends the READ , and \$ZB contains the full sequence, including the leading Escape. InterSystems IRIS does not echo the characters of the sequence, but it does change \$X and \$Y unless you include the escape sequence in a <code>WRITE *</code> command. See \$X and \$Y and Cursor Position earlier on this page. An invalid escape sequence sets bit 8 of \$ZA . Consider the example, <code>READ X</code> . After you enter the characters "AB", Escape , and "E", X will contain the two characters "AB", while \$ZB contains the two characters Escape E. \$X increases by two for the AB, but does not increase for the E.
LineFeed	10	InterSystems IRIS interprets LineFeed as a terminator for all terminal I/O.
Tab	9	Tab is a data value that echoes as a space, increases \$X by one, and is stored as a Tab character in the string returned by the READ . This is true for all protocols except "T" (terminator). In "T" protocol, a tab is a terminator control character.

9.4.4.1 Disabling UNIX® Job Control

Using the UNIX® job control character, **Ctrl-Z**, within InterSystems IRIS can cause serious problems. For this reason, InterSystems IRIS disables **Ctrl-Z** automatically when you enter InterSystems IRIS on platforms whose UNIX® shell supports job control. InterSystems IRIS reenables **Ctrl-Z** when you exit InterSystems, and when you issue a **\$ZF(-1)** call to execute a UNIX® shell command.

9.4.5 How the READ Command Processes Input

The **READ** command processes each character as it arrives from the input buffer. The following table shows how this processing occurs in normal mode. The figure below shows how the **READ** command processes image mode data.

Figure 9–1: READ Command Processing Normal (Non-Image) Mode





Figure 9–2: READ Command Processing Image Mode



9.5 WRITE Command

Writes zero or more characters to the terminal.

9.5.1 Syntax

```
WRITE *variable
WRITE *-n
WRITE #
WRITE /mnemonic
```

where

Argument	Definition
(none)	WRITE with no arguments writes all local variables on the current device.
*variable	WRITE *variable writes one character, whose decimal value equals x. The value of variable should be an integer in the range 0 to 255 for ASCII characters, and >255 for Unicode characters. By convention, values from 0 to 127 signify 7 bit ASCII characters, while 128 to 255, which represent the extended ASCII character set, relate to the application itself. If the hardware and software are properly set, InterSystems IRIS can handle 8 bit data. Example : You can use the eighth bit to represent international character sets. InterSystems IRIS routines often use WRITE * to send control characters for device dependent functions. Example : WRITE *27,*91,*50,*74 clears the terminal screen. WRITE * does not change \$X or \$Y ; the assumption is that WRITE * output is highly specific to the output device.
*-1	WRITE *-1 clears the input buffer when the next READ is issued. It clears any characters that are pending for the next READ command. Thus all type-ahead characters are cleared. An input buffer holds characters as they arrive from the keyboard, even those you type before the routine executes a READ command. Thus you can answer questions even before they appear on the screen. When the READ command takes characters from the buffer, InterSystems IRIS echoes them back to the terminal so that questions and answers appear together. When a routine detects errors, it may issue WRITE *-1 to cancel these answers.
*-10	WRITE *-10 clears the input buffer immediately. It does not wait for the next READ command. Thus it clears all type-ahead characters issued before the WRITE *-10; type-ahead characters issued after the WRITE *-10 remain in the input buffer for use by the next READ .

Argument	Definition
#	Issuing <code>WRITE #</code> to a CRT terminal clears the screen and sends the cursor to the home (0,0) position. For a hardcopy terminal, it writes a Carriage Return and Form Feed. <code>WRITE #</code> sets \$Y to 0.
/mnemonic	Issuing <code>WRITE /mnemonic</code> causes InterSystems IRIS to interpret mnemonic as defined in the active mnemonic space. If there is no active mnemonic space, an error results. You can specify the active mnemonic space in two ways: By naming a default mnemonic space for each device type using the Namespace and Network Configuration editor by specifying a mnemonic space in the OPEN or USE command for the device. For more information, see Controlling Devices with Mnemonic Spaces .

For more information, see [WRITE](#) in the *ObjectScript Language Reference*.

9.5.2 Examples

In the following example, `WRITE *` rings the bell on the user's terminal, displays a prompt, and clears the input buffer of any characters received but not yet used.

ObjectScript

```
SET eek="No. I can't accept that reply"
WRITE *7,eek,*-10
```

The following two examples show the difference between `WRITE *-1` and `WRITE *-10`. In both cases, the user responds to the first **READ** and presses ENTER, then types ahead during the two pauses caused by the **HANG** commands:

ObjectScript

```
READ "type:",x HANG 4 WRITE *-1 HANG 4 READ "type:",y
```

In the above example, InterSystems IRIS clears the input buffer when the second **READ** is issued. Thus any text typed during either **HANG** is cleared from the buffer.

ObjectScript

```
READ "type:",x HANG 4 WRITE *-10 HANG 4 READ "type:",y
```

In the above example, InterSystems IRIS immediately clears the input buffer when `WRITE *-10` is issued. Thus any text typed during the first **HANG** is cleared, but any text typed during the second **HANG** is supplied to the second **READ** command.

In the following example, `WRITE /mnemonic` uses the control mnemonic CUP (CURsor Position) to move the cursor to the third column of the fourth line on the Terminal. In this example, the predefined mnemonic space `^%X364` is specified in the **USE** command, and the name of an open Terminal device is specified using the `terminal` variable. See [Predefined Mnemonic Spaces for Terminals](#) for a description of `^%X364`.

ObjectScript

```
USE terminal:(80:"BP"):"%X364"
SET %1=3,%2=4
WRITE /CUP(%1,%2)
```

9.6 CLOSE Command

Releases ownership of the device, which is gained with an **OPEN** command.

9.6.1 Syntax

```
CLOSE device
```

For more information, see [CLOSE](#) in the *ObjectScript Language Reference*.

9.7 Predefined Mnemonic Spaces for Terminals

InterSystems IRIS provides two predefined mnemonic spaces for use with terminals:

- `^%X364` for ANSI X3.64 terminals
- `^%XDTM` for DTM PC Console

If you make one of these mnemonic spaces active, you can use the control mnemonics associated with them in `WRITE` /`mnemonic` commands. You can also create your own mnemonic spaces. See [Controlling Devices with Mnemonic Spaces](#) for more information on mnemonic spaces.

The following sections describe the control mnemonics for these mnemonic spaces.

9.7.1 Mnemonic Space for X3.64

InterSystems IRIS provides a built-in mnemonic space for the ANSI X3.64 definition. This mnemonic space is the InterSystems IRIS routine `%X364` in the manager's namespace. To use routine `%X364`, either:

- Have your InterSystems IRIS system manager enter `%X364` as the default mnemonic space in the **IO Settings** configuration setting. From the Management Portal, select **System Administration, Configuration, Device Settings, IO Settings**.
- Issue an **OPEN** command specifying this mnemonic space:

ObjectScript

```
OPEN "terminal"::"^%X364"
```

The following table lists the mnemonics.

Table 9–9: Control Mnemonics for %X364 Mnemonic Space

Calling Sequence	Name	System Variable Affected
APC	Application Program Command	
BEL	Ring the bell	
CBT(%1)	Cursor Backward Tabulation	\$X
CCH	Cancel Character	

Calling Sequence	Name	System Variable Affected
CHA(%1)	Cursor Horizontal Absolute	\$X
CHT(%1)	Cursor Horizontal Tabulation	\$X
CNL(%1)	Cursor Next Line	\$X,\$Y
CPL(%1)	Cursor Preceding Line	\$X,\$Y
CPR	Cursor Position Report	
CTC(%1,%2,%3,%4, %5,%6,%7,%8,%9)	Cursor Tabulation Control	
CUB(%1)	Cursor Backward	\$X
CUD(%1)	Cursor Down	\$Y
CUF(%1)	Cursor Forward	\$X
CUP(%1,%2)	Cursor Position	\$X, \$Y
CUU(%1)	Cursor Up	\$Y
CVT(%1)	Cursor Vertical Tabulation	\$Y
DA	Device Attributes	
DAQ(%1,%2,%3,%4, %5,%6,%7,%8,%9)	Define Area Qualification	
DCH(%1)	Delete Characters	
DCS	Device Control String	
DL(%1)	Delete Lines	
DMI	Disable Manual Input	
DSR(%1)	Device Status Report	
EA(%1)	Erase in Area	
ECH(%1)	Erase Characters	
ED(%1)	Erase in Display	
EF(%1)	Erase in Field	
EL(%1)	Erase in Line	
EMI	Enable Manual Input	
EPA	End of Protected Area	
ESA	End of Selected Area	
FNT	Font Selection	
GSM	Graphic Size Modification	
GSS	Graphic Size Selection	
HPA(%1)	Horizontal Position Attribute	\$X

Calling Sequence	Name	System Variable Affected
HPR(%1)	Horizontal Position Relative	\$X
HTJ	Horizontal Tab with Justify	\$X
HTS	Horizontal Tab Set	\$X
HVP(%1,%2)	Horizontal and vertical position	\$X, \$Y
ICH(%1)	Insert Characters	
IL(%1)	Insert Lines	
IND	Index	\$Y
INT	Interrupt	
JFY	Justify	
MC	Media Copy	
MW	Message Waiting	
NEL	Next Line	\$X, \$Y
NP(%1)	Next Page	
OSC	Operating System Command	
PLD	Partial Line Down	\$Y
PLU	Partial Line Up	\$Y
PM	Privacy Message	
PP(%1)	Preceding Page	
PU1	Private Use 1	
PU2	Private Use 2	
QUAD	QUAD	
REP(%1)	REPEAT	\$X, \$Y
RI	Reverse Index	\$Y
RIS	Reset to Initial State	\$X=0 \$Y=0
RM(%1,%2,%3,%4,%5,%6,%7,%8,%9)	Reset Mode	
SEM	Select Editing Extent Mode	
SGR(%1,%2,%3,%4,%5,%6,%7,%8,%9)	Select Graphic Rendition	
SL	Scroll Left	
SM(%1,%2,%3,%4,%5,%6,%7,%8,%9)	Set Mode	
SPA	Start of Protected Area	

Calling Sequence	Name	System Variable Affected
SPI	Spacing Increment	
SR	Scroll Right	
SS2	Single Shift Two	
SS3	Single Shift Three	
SSA	Start of Selected Area	
ST	String Terminator	
STS	Set Transmit State	
SU	Scroll Up	
TBC	Tabulation Clear	
TSS	Thin Space Specification	
VPA(%1)	Vertical Position Attribute	\$Y
VPR(%1)	Vertical Position Relative	\$Y
VTS	Vertical Tab Set	

9.7.2 Mnemonic Space for DTM PC Console

InterSystems IRIS provides the InterSystems IRIS routine %XDTM to match the mnemonics used in developing applications for DTM. This mnemonic space is available but is not set up as the default mnemonic space for terminals. If you port applications created for DTM to InterSystems IRIS, you can either:

- Configure ^%XDTM as the default mnemonic space for terminals (**MnemonicTerminal**) in the Management Portal, or
- Reference the ^%XDTM mnemonic space in the **OPEN** or **USE** command.

9.7.3 DTM Examples

9.7.3.1 UNIX®

ObjectScript

```
OPEN "/dev/tty04/"::" ^%XDTM"
```

9.7.3.2 Windows

ObjectScript

```
OPEN "c:\sys\user"::" ^%XDTM"
```

Then InterSystems IRIS can correctly interpret the DTM control mnemonics in `WRITE /mnemonic` commands, shown in the following table.

Table 9–10: Control Mnemonics for DTM PC Console

Mnemonic	Description
AA	Normal mode
AB	Bold mode
AC	Underlined mode
AD	Bold, underlined mode
AE	Reverse video
AF	Reverse video/Bold mode
AG	Reverse video/Underline mode
AH	Reverse video/Bold, underlined mode
AI	Blink mode
AJ	Bold, blink mode
AK	Underlined, blink mode
AL	Bold, underlined, blink mode
AM	Reverse video / Bold, blink mode
AN	Reverse video / Bold, blink mode
AO	Reverse video / Underlined, blink modes
AP	Reverse video / Bold, underlined, blink modes
AZ	Mode Z
B(%1,%2)	Set video attributes: %1 provides attribute for characters, %2 provides attribute for clearing frames
BOX	Draw a window-relative utility box
C(%1,%2)	Position cursor at column %1, line %2
CLR	Clear current frame
COLOR(%1,%2)	Set IBM PC Color: Foreground %1, Background %2
DC(%1)	Delete %1 characters
EC(%1)	Erase %1 characters
EF	Erase to end of frame
EL	Erase to end of line
F(%1,%2,%3, %4,%5)	Fill rectangular area with \$CHAR(%1) at upper left corner, %4 columns wide by %5 lines high
GETCUR	Return terminal cursor position
HF	Screen half bright off
HIDECURSOR	Hide mouse cursor
HN	Screen half bright

Mnemonic	Description
IC(%1)	Insert %1 characters
LF	Disable literal mode
LN	Enable literal mode, which displays control characters graphically on a PC screen.
MARK(%1)	Make mark on screen
NORM	Enable normal display attributes
PAD(%1)	Write %1 NULLS for padding
PF	Pause off
PN	Pause on
RF	Screen reverse video off
RN	Screen reverse video
SD(%1,%2,%3)	Scroll current frame down by %3 lines
SHOWCURSOR	Show mouse cursor
SU(%1,%2,%3)	Scroll current frame up by %3 lines, starting at line %1 down to but not including line %2
VF	Visible cursor off
VN	Visible cursor on
WBOX	Draw a screen-relative utility box
WCLOSE	Close utility window
WINDOW	Set scrolling window
WOPEN	Open utility window
Y(%1)	Set binary frame attribute

9.8 PRINT and ZPRINT Commands

Writes one or more lines of the currently loaded InterSystems IRIS routine to the current device.

ZPRINT has the same effect and arguments as **PRINT**.

9.8.1 Syntax

```
PRINT
ZPRINT
PRINT x
ZPRINT x
PRINT x:y
ZPRINT x:y
```

where

Argument	Definition
(none)	The PRINT or ZPRINT command with no arguments prints the entire routine.
x,y	The variables <i>x</i> and <i>y</i> indicate the range of lines to print. They can be either a line reference of the form TAG+OFFSET, or a line number of the form +7. Referring to a line not in the routine implies the empty line following the routine's last line. <i>x</i> = First or only line to print. <i>y</i> = Last line to print.

For more information, see [PRINT](#) in the *ObjectScript Language Reference*.

9.8.1.1 Example

This example prints the first line of the current routine, four lines starting at INIT, and all the lines from FINI to the end:

ObjectScript

```
INIT
  SET a=1
  SET b=2
  SET c=3
  SET d=4
FINI
  SET x=24
  SET y=25
  SET z=26
  PRINT +1, INIT:INIT+3, FINI:+9999
```

9.9 Programming Your Terminal

9.9.1 Using InterSystems IRIS to Program Formatted CRT Screens

Several features of Terminal I/O aid in programming formatted screens:

- Use **WRITE *** to send control sequences easily.
- Use **READ** to receive escape-sequence responses.
- Use **SET \$X = expression** and **SET \$Y = expression** to update the current cursor position.

Fixed-length **READ** and programmer-specified termination characters make it convenient to read individual fields. You can use the Secret protocol to make passwords invisible.

Remember that **WRITE *** does not change **\$X** or **\$Y**. If you want to change them, use **WRITE \$C(X)**, or simply set them explicitly.

9.9.1.1 Example

This example sets the VT100 cursor to line 10, column 20

```
%SYS>SET DY=10,DX=20
%SYS>WRITE *27,*91,DY+1,*59,DX+1,*72 SET $Y=DY,$X=DX
```

9.9.1.2 Use CURRENT^%IS to Set Variables

The utility routine CURRENT^%IS sets some useful local variables to work for the current device. To call this routine, enter:

```
%SYS>DO CURRENT^%IS
```

This command sets the variables indicated in the following table.

Table 9–11: Features Enabled By CURRENT^%IS

Code	Definition
W @FF	Clears the screen and moves the cursor to the upper left corner (column 0, line 0) leaving \$X=0 , \$Y=0 .
S DX=42,DY=10 X XY	Moves the cursor directly to column 42, line 10, leaving \$X=42 , \$Y=10 .

9.9.2 Programming Escape Sequences

The ANSI standard for escape sequences makes programming of smart terminals practical. The **Escape** character and all characters after it in a string do not display on the screen, but do update **\$X** and **\$Y**. Send escape sequences to the terminal with `WRITE *` statements and keep **\$X** and **\$Y** up to date by setting them directly.

The ANSI standard establishes a standard syntax for escape sequences. The effect of a particular escape sequence depends on the type of terminal you are using.

Look for incoming escape sequences in **\$ZB** after each **READ**. InterSystems IRIS puts ANSI-standard escape sequences and any others that use the ANSI forms in **\$ZB**. InterSystems IRIS recognizes two forms of escape sequence:

9.9.2.1 Regular form

- An **ESC**.
- Optionally the character “O” (the letter), decimal value 79.
- Zero or more characters with decimal values 32–47.
- One character with decimal value 48–126.

9.9.2.2 Control form

- The **ESC** character, decimal value 27.
- The “[” character, decimal value 91.
- Zero or more characters with decimal values 48–63.
- Zero or more characters with decimal values 32–47.
- One character with decimal value 64–126.

Furthermore, the sequence can be no longer than 16 characters. Escape sequences that violate these forms or rules set bit 8 of **\$ZA**, whose value is 256.

9.9.3 Example

Assume that you are programming a terminal whose **Help** key sends the two-character sequence **Escape-?** (? has a decimal value of 63)

```
%SYS>SET HELP=$C(27,63)
ASK READ !,"Enter ID: ",X I $ZB=HELP Do GIVEHELP GoTo ASK
```

Your routine can detect nonstandard escape sequences as follows:

1. Make **ESC** a terminator.
2. When **ESC** appears in **\$ZB**:
 - a. Disable echo with the Secret protocol to prevent modification of **\$X/\$Y**.
 - b. Read the rest of the sequence with **READ ***;
 - c. Turn off Secret to re-enable echo.

In the following figure, the user is asked to enter an ID. If the user presses **Esc-?**, a Help screen appears. The subroutine **ESCSEQ** assumes that nonstandard escape sequences end with an asterisk **"**"**.

ObjectScript

```
DEMOS
  SET HELP=$C(27,63) ;Get Help with <ESC>?
  SET ESC=$C(27) USE 0:("":":ESC) ; Make <ESC> a READ terminator
                                ; character
ASK READ !,"Enter ID: ",X I $ZB=ESC Do ESCSEQ G:SEQ=HELP ASK
. ;Input ID. Handle Help request.
.
  Quit
HELPSCR ;Process Help request
.
  Quit
ESCSEQ USE 0:("":":S") SET SEQ=ESC ;Set terminal to no echo,init SEQ
FOR I=1:1 {
  READ *Y
  SET SEQ=SEQ_$C(Y)
  QUIT:Y=42 }
; Read in Escape sequence,
; end at "**"
USE 0:("":":ESC) Quit ;Redefine terminator
```

9.9.4 InterSystems IRIS Supports Full or Half Duplex and Echo

InterSystems IRIS prefers that you use full duplex terminals; in other words, your keyboard should operate independently from your printer or screen.

Full duplex means simultaneous and independent transmission in both directions. Half duplex means transmission in only one direction at a time. Duplex has nothing to do with echo, although you may see a terminal marked full duplex for remote echo and half duplex for local echo. This designation means that the terminal displays the characters you type and does not expect InterSystems IRIS to echo them.

Set your terminal to local echo off or full duplex, letting InterSystems IRIS provide the echo. The echo comes not when the computer receives the character, but when the **READ** command takes it from the input buffer; therefore, the prompts and answers of a dialog keep their intended positions on the screen regardless of whether the user types ahead.

Some public networks provide their own echo to the terminal.

On Windows systems, consoles do not permit local echo setup changes. For terminals attached via a terminal emulator (e.g., VT220), refer to your terminal emulator documentation for instructions to disable local echo.

On UNIX® systems, use the **stty** command to avoid double echoes while keeping **\$X** and **\$Y** in agreement with the cursor's position.

9.9.5 InterSystems IRIS Supports Intercomputer Links and Special Devices

InterSystems IRIS provides flexible protocols and large independent buffers enable routines to deal with unusual devices and their protocols. For example, InterSystems IRIS easily supports full duplex communication between two computers on a terminal-to-terminal link. Two InterSystems IRIS systems require only a physical connection, the right protocols, and identical settings of speed, parity, and character length. With the aid of external converters, InterSystems IRIS communicates with IBM ports as a synchronous EBCDIC terminal.

Keep these points in mind when designing an intercomputer link:

- Turn off echo at both ends by including the S protocol in **OPEN** or **USE**, or by using the operating system's terminal parameters.
- Unless your communication protocol supports XON/XOFF flow control (**Ctrl-Q** and **Ctrl-S**), be sure it limits unacknowledged transmissions to the limit of the operating system's input buffering; otherwise you may lose data.
- In image mode, InterSystems IRIS does not support XON/XOFF. In nonimage (normal) mode, the operating system's terminal parameters determine whether the computer issues an XOFF if the operating system's input buffer is almost full. If XOFF and XON are not supported, make the buffer large enough that you do not need them.
- Test **\$ZA** after read operations to detect transmission errors such as parity or data overrun conditions.

10

File I/O

This page describes using sequential files in InterSystems IRIS® data platform.

Important: In most cases, you may be able to use the API provided by the `%Library.File` class instead of needing the detailed information on this page. See [Using %Library.File](#).

10.1 Introduction

All operating systems consider disk I/O files as sequential files. Windows systems consider printers as sequential file I/O devices (unless the printer is connected through a serial communications port). UNIX® systems consider printers as terminal I/O devices. For further details on printers, see [Printers](#).

This section discusses how InterSystems IRIS processes sequential files. It provides an introduction to sequential file I/O and descriptions of the relevant commands.

- To gain access to a sequential file, you must first open the file using the **OPEN** command, supplying the name of the file as an argument. You also, optionally, specify **OPEN** mode parameters. If the **OPEN** specifies a file that does not exist, a mode parameter specifies whether or not to create a new file. You can open multiple files concurrently.
- After opening a sequential file, you must specify a **USE** command to access the file, supplying the name of the file as an argument. The **USE** command makes the specified file the current device; therefore you can only use one file at a time. The **USE** command can also specify mode parameters.
- You then can issue multiple **READ** or **WRITE** commands against the file. Each **READ** or **WRITE** command delivers one record to or from the file. You cannot write to the file unless it has been opened with the “W” mode parameter. Attempting to read past the end of the file causes an `<ENDOFFILE>` error.
- You can use the **\$ZSEEK** function to set the file position, specified by character count offset from the beginning, current position, or end of the sequential file. The **\$ZPOS** special variable contains the current character count position from the beginning of the current sequential file.
- Once you have completed file I/O, you issue a **CLOSE** command to close the sequential file.

These operations can also be performed using the methods of the `%Library.File` class.

The `%Library.File.Exists()` method tells you whether a sequential file with the specified name already exists.

The `%Library.File.Size` property returns the number of characters currently in the sequential file.

The `%Library.File.DateModified` property is updated with the current local date and time when a file is opened, and—if it has been modified—when it is closed.

The `%Library.File.IsOpen` property only returns 1 if the file has been opened by the `%Library.File.Open()` method; the **OPEN** command does not set this boolean property.

10.2 Specifying a File

A sequential file can be specified by a canonical (full) pathname or a relative (partial) pathname that the system expands to a full pathname. A pathname can be canonical (`c:\InterSystems\IRIS\mgr\user\myfiles\testfile.txt`) or relative to the current directory (`testfile.txt`). A leading period (`.`) specifies the current directory. A leading double period (`..`) specifies the parent of the current directory. If the **OPEN** command creates a new file, the specified directory must already exist.

A file access error returned by the operating system, such as `The system cannot find the file specified` is returned by the `%SYSTEM.Process.OSError()` method. This method returns the operating system error number enclosed in angle brackets, followed by the error text. This is shown in the following Windows example:

```
USER>OPEN "C:\InterSystems\IRIS\mgr\nodir\testfile.txt":("WNS"):5
USER>w $SYSTEM.Process.OSError()
<3> The system cannot find the path specified.
USER>w ##class(%File).TempFilename("txt","C:\InterSystems\IRIS\mgr\nodir\testfile",.oserrnum)
USER>w $SYSTEM.Process.OSError()
<3> The system cannot find the path specified.
```

The following Windows examples all create a file in the current namespace (USER) directory:

- full pathname: `OPEN "C:\InterSystems\IRIS\mgr\user\testfile1.txt":("WNS"):10`
- filename expansion: `OPEN "testfile2.txt":("WNS"):10`
- current directory expansion: `OPEN ".\testfile3.txt":("WNS"):10`

The following Windows example creates a file in an existing child directory of the current namespace (USER) directory:

- child of current directory: `OPEN "mytemp\testfile4.txt":("WNS"):10`

The following Windows examples create a file using parent directory (`..`) syntax:

- parent directory (`C:\InterSystems\IRIS\mgr\`): `OPEN "..\testfile5.txt":("WNS"):10`
- current directory (child of parent directory) `C:\InterSystems\IRIS\mgr\user\`: `OPEN "..\user\testfile6.txt":("WNS"):10.`
- another child of parent directory `C:\InterSystems\IRIS\mgr\temp\`: `OPEN "..\temp\testfile7.txt":("WNS"):10.`
- parent of parent directory `C:\InterSystems\IRIS\`: `OPEN "..\..\testfile8.txt":("WNS"):10.`

Windows pathnames use a `\` (backslash) directory separator; UNIX pathnames use a `/` (slash) directory separator. Valid characters may be 8-bit ASCII, or ISO Latin-1 Unicode.

A Windows file pathname specification has the following format:

```
device:\directory\file.type
```

For example, `C:\InterSystems\IRIS\mgr\user\myfiles\testfile.txt`. The *type* suffix is optional.

A UNIX® file pathname specification has the following format:

```
../directory/name
```

A file pathname must not exceed 256 characters when fully expanded. If the pathname length of all directories exceeds 256, a <DIRECTORY> error is generated. If the pathname length exceeds 256 because of the length of the filename, a <NAMEADD> error is generated.

A UNIX® file pathname can include up to 255 characters of any type. While the characters period (“.”) and underscore (“_”) can appear anywhere in the filename, you typically use them to divide the name into meaningful parts. For example, you can define a filename `pat_rec.dat`, using `.dat` as the file type.

When accessing files in the current UNIX® default directory, you usually need to specify only the name. The system fills in default values for the directory.

A DLL name can be specified as a full pathname, or a partial pathname. If you specify a partial pathname, InterSystems IRIS expands it to the current directory. Generally, DLLs are stored in the binary directory (“bin”). To locate the binary directory, call the **BinaryDirectory()** method of the `%SYSTEM.Util` class.

10.2.1 File Pathname Tools

If the current device is a sequential file, `$ZIO` contains the full pathname of that file.

You can use `$ZSEARCH` to return the full file specification (pathname and filename) of a specified file or directory. The filename may contain wild cards that `$ZSEARCH` uses to return a series of fully qualified pathnames that satisfy the wild carding.

The `%Library.File` class contains numerous methods that provide file system services. These include:

- **NormalizeDirectory()**, which returns the full pathname of a specified file or directory.
- **NormalizeFilenameWithSpaces()**, which handles spaces in pathnames as appropriate for the host platform. If a pathname contains a space character, pathname handling is platform-dependent. Windows and UNIX® permit space characters in pathnames, but the entire pathname containing spaces must be enclosed in an additional set of double quote (“”) characters. This is in accordance with the Windows `cmd /c` statement. For further details, specify `cmd /?` at the Windows command prompt.

10.2.2 Tilde (~) Expansion

In Windows pathnames, a tilde (~) indicates 8.3 compression of long names. For example: `c:\PROGRA~1\`. To convert compressed directory names, use the **NormalizeDirectory()** method of the `%Library.File` class.

In UNIX® pathnames, you can use tilde (~) expansion to indicate the current user’s home directory or the home directory of a specified user:

- `~` and `~/myfile.txt` are expanded to the current user's home directory: `/Users/techwriter/` and `/Users/techwriter/myfile.txt`, respectively.
- `~guest/myfile.txt` is expanded to the home directory of user “guest”: `/Users/guest/myfile.txt`. However, if user “guest” does not exist, InterSystems IRIS expands to the current user's full directory pathname and appends `~guest/myfile.txt` as a literal: `/Users/techwriter/iris/mgr/user/~guest/myfile.txt`.
- `~myfile.txt` and `~123.txt` are appended to the current user's full directory pathname as a literal: `/Users/techwriter/iris/mgr/user/~myfile.txt` and `/Users/techwriter/iris/mgr/user/~123.txt`, respectively.

10.3 OPEN Command

OPEN opens a sequential file. Remember that you cannot use the **OPEN** command to open an InterSystems IRIS database file.

The **OPEN** command by itself does not prevent another process from opening the same sequential file. You can govern concurrent sequential file access by using the **OPEN** command “L” mode parameter and/or the ObjectScript **LOCK** command. File locking support is provided by the file access rules of the underlying operating system.

InterSystems IRIS allocates each process' open file quota between database files and files opened with the ObjectScript **OPEN** command. When an **OPEN** command causes too many files to be allocated to **OPEN** commands, a <TOOMANYFILES> error occurs. The InterSystems IRIS maximum number of open files for a process is 1,024. The actual maximum number of open files for each process is a platform-specific setting. For example, Windows defaults to a maximum of 998 open files per process. Consult the operating system documentation for your system.

10.3.1 OPEN Syntax

```
OPEN filename{{:({parameters{:reclength{:terminators}}})}{:timeout}}
```

where

filename

Any valid [file specification](#), enclosed in quotation marks. This file pathname must not exceed 255 characters. Valid characters may be 8-bit ASCII, or ISO Latin-1 Unicode. In UNIX pathnames, you can use tilde (~) expansion to indicate the current user's home directory. For example: ~/myfile or ~/myfile.

parameters

Optional — A string of one-letter codes, enclosed in quotation marks, that define the file format and types of operations you can perform. (You may also specify *parameters* using keywords that begin with the slash (/) character.) See the table [OPEN Mode Parameters](#) for definitions of these codes. If the parameters do not include R or W, then R is the default. This system-wide default open mode can be configured by setting the *OpenMode* property of the Config.Miscellaneous class. To open a new file, you must specify the parameter N for new. Otherwise, the **OPEN** will hang or return unsuccessfully from a timeout. If the parameters do not include S, V, F, or U, then the default for a new Windows or UNIX® file is S, and the default for an existing file is the mode specified when the file was created. If A is not specified, **WRITE** operations will overwrite the previous contents of the file. Parameters are applied in left-to-right order.

reclen

Optional — For Windows and UNIX systems, specifies the maximum record length for (S) and (U) records, or the absolute record length for fixed-length (F) records. Ignored for variable-length (V) records. Default value is 32767.

terminators

Optional — A string of user-defined record terminators that apply to stream mode only. They let you override the default terminators: carriage return, line feed, and form feed. User-defined terminators only apply to input, they do not affect how data is written to the file (terminators are written to a file as special characters). If there's more than one user-defined terminator, it is treated as a list of terminators, not a multi-character sequence to be used as a single terminator.

timeout

Optional — Number of seconds during which InterSystems IRIS attempts to open the file. If it does not succeed within this interval, it sets **\$TEST** to 0 and returns control to the process. If it succeeds, it sets **\$TEST** to 1.

The *timeout* argument, though optional, is strongly recommended because the success or failure of **OPEN** is indicated by the value of the **\$TEST** special variable, and **\$TEST** is only set if *timeout* is specified. **\$TEST** is set to 1 if the open attempt succeeds before the timeout expires; if the timeout expires, **\$TEST** is set to 0.

10.3.2 OPEN Mode Parameters

You can specify the **OPEN** mode parameters in either of two ways:

- A letter code string, such as “VRWN”, enclosed in quote characters. Each letter specifies a parameter. Letter codes may be specified in any order; because InterSystems IRIS executes them in left-to-right order, interactions between letter codes may dictate a preferred order in some cases.
- A series of */keyword* parameters, not quoted. These parameters are separated by colons. Keyword parameters may be specified in any order; because InterSystems IRIS executes them in left-to-right order, interactions between parameters may dictate a preferred order in some cases.

When specifying a combination of letter code parameters and keyword parameters, specify the letter code string first, followed by the keyword parameter(s), separated with colons. The following example specifies three letter code parameters, followed by two keyword parameters, followed by the *reclen* and *timeout* arguments.

ObjectScript

```
OPEN "mytest": ("WNS": /OBUFSIZE=65536: /GZIP=0:32767):10
```

Table 10–1: OPEN Mode Parameters

Letter Code	Keyword	Description
N	/NEW	New file. If the specified file does not exist, the system creates the file. If the specified file already exists as a ReadOnly file, the system deletes the old file and replaces it with a new one with the same name (permissions permitting). Note that file locking should be used to prevent concurrent processes using this parameter overwriting the same file. If the “N” mode (or the “T” mode) is not specified and the file specified in OPEN does not exist, the Windows and UNIX® default is to not create a new file. This behavior is configurable using the FileMode() method of the %SYSTEM.Process class. The system-wide default behavior can be established by setting the <i>FileMode</i> property of the Config.Miscellaneous class.
E	/CREATE or /CRE	Create a file if it does not exist. Does not delete and recreate an existing file, as the “N” mode does. The default is to not create a new file. This default is overridden if the FileMode() method of the %SYSTEM.Process class, or the <i>FileMode</i> property of the Config.Miscellaneous class is enabled.
T	/TRUNCATE	Truncate File: If the file exists and is writable it will be truncated and its attributes left unchanged. If the specified file does not exist, the system creates a new file, just as if the “N” mode was specified. “WT” and “WNT” are functionally identical.

Letter Code	Keyword	Description
D	/DELETE[= <i>n</i>] <i>or</i> /DEL[= <i>n</i>]	Delete File: Specifies that the file should be automatically deleted when it is closed. /DELETE or /DELETE= <i>n</i> for nonzero values of <i>n</i> enable the parameter code. /DELETE= <i>n</i> for a zero value of <i>n</i> disables the parameter code. The default is to not delete a file.
R	/READ	Read: InterSystems IRIS permits READ access the file. Other processes may also access this file (however, see “L” parameter). If you attempt to open a nonexistent file in “R” mode, the process hangs. To prevent this situation, use a timeout. “R” is the default for all platforms. The system-wide default open mode can be configured by setting the <i>OpenMode</i> property of the Config.Miscellaneous class.
W	/WRITE <i>or</i> /WRI	Write: InterSystems IRIS permits WRITE access to the file. In Windows and UNIX®, “W” gives the process shared write access to the file, with exclusive write access to the record. Use “WL” to specify exclusive write access to the file. If you attempt to open a nonexistent file in “W” mode, the process hangs until the file is created or the process is resolved by a timeout, a Process Terminate, or RESJOB. “R” is the default for all platforms. The system-wide default open mode can be configured by setting the <i>OpenMode</i> property of the Config.Miscellaneous class. Can be used with /OBUFSIZE.
L		Locked Exclusive: Use the “L” mode with the “W” (Write) mode to specify exclusive write access to a file. “WL” or “WRL” specifies that the current process has exclusive write access to the file. A file opened with “RL” may still have shared read access. The effects of the “L” mode on concurrent opens are different in Windows and UNIX®. Refer to the “OPEN Mode Locking” section, below, for further details. On UNIX® systems if one process specifies “WL” (or “WRL”) access to a file, other processes requesting read access to that file must specify “RL” so that UNIX® can coordinate file locking.
A	/APPEND <i>or</i> /APP	Append: WRITE operations append data to the end of an existing file. The default is to overwrite existing data, rather than append.
S	/STREAM	Stream format with carriage return, line feed, or form feed as default terminators. S, V, F, and U modes are mutually exclusive. Stream record format is the default.

Letter Code	Keyword	Description
V	/VARIABLE	<p>Variable length: Each WRITE creates one record. For Windows and UNIX®, a variable record can be of any length; the <i>reclen</i> argument is ignored.</p> <p>Do not attempt to insert records at any point other than the end of a variable-length sequential file; a WRITE will render inaccessible all data in the file from the point after the WRITE on. S, V, F, and U modes are mutually exclusive. Stream record (S) format is the default.</p> <p>A variable-length record written using a translation table, such as Unicode data using UTF8 translation, can result in a stored record with a different string length than the input data. InterSystems IRIS uses the original input string length when reading this record.</p>
F	/FIXED or /FIX	<p>Fixed length: Each record is the length specified in the <i>reclen</i> argument. For example:</p> <p>ObjectScript</p> <pre>OPEN "myfile":("RF":4) USE "myfile":0 READ x:5</pre> <p>This example reads the first 4-character record into the variable x. This works only for READ operations (not WRITE operations). S, V, F, and U modes are mutually exclusive.</p>
U	/UNDEFINED	<p>Undefined length: Specifies that file records have an undefined length and therefore READ operations must specify the number of characters to read. The maximum record length is specified in the <i>reclen</i> argument. No translation on output. Default value is the maximum string length. S, V, F, and U modes are mutually exclusive.</p>
K\name\ or Knum	/TRANSLATE[=n]: /IOTABLE[=name] or /TRA[=n]: /IOT[=name]	<p>I/O Translation Mode: When you use the “K” parameter for a device, I/O translation will occur for that device if translation has been enabled system-wide. You identify the previously defined table on which the translation is based by specifying the table's name. When using keywords you specify /TRANSLATE to enable I/O translation (<i>n</i>=1 to enable; <i>n</i>=0 to disable), and /IOTABLE=<i>name</i> to specify the translation table to use. For a list of available translation tables, see Encoded Translation in the \$ZCONVERT function documentation. The + and - options for turning protocols on and off are not available with the K protocol. (The older form Knum, where “num” represents the number of the slot the table is loaded in, is being phased out but is still supported. The system manager can display slot numbers in the %NLS utility in the selection window for each table type.) This parameter may be used with either the OPEN command or the USE command.</p>

Letter Code	Keyword	Description
Yname\ or Ynum	/XYTABLE[= <i>name</i>] or /XYT[= <i>name</i>]	\$X/\$Y Action Mode: When you use the “Y” parameter for a device, the system uses the named \$X/\$Y Action Table. You identify the previously defined \$X/\$Y Action Table on which translation is based by specifying the table's name. \$X/\$Y action is always enabled. If “Y” is not specified and a system default \$X/\$Y is not defined, a built in \$X/\$Y action table is used. The + and - options for turning protocols on and off are not available with the Y protocol. (The older form Ynum, where “num” represents the number of the slot the table is loaded in, is being phased out but is still supported. The system manager can display slot numbers in the NLS utility in the selection window for each table type.) This parameter may be used with either the OPEN command or the USE command.
	/NOXY [= <i>n</i>]	No \$X and \$Y processing: /NOXY or /NOXY= <i>n</i> (for nonzero values of <i>n</i>) disables \$X and \$Y processing. This can substantially improve performance of READ and WRITE operations. The values of the \$X and \$Y variables are indeterminate, and margin processing (which depends on \$X) is disabled. /NOXY=0 enables \$X and \$Y processing; this is the default. This parameter may be used with either the OPEN command or the USE command.
	/OBUFSIZE= <i>int</i>	Output Buffering: Creates an output WRITE buffer. The <i>int</i> variable is an integer that specifies the size of the buffer in bytes. May only be used when the file is open for write only (“W”, not “R” or “RW”). May provide significant performance improvement when performing multiple small writes, especially over a WAN. However, data in buffer may be lost if a system crash occurs. Data in buffer is flushed to disk upon CLOSE , or WRITE *-1 or WRITE *-3 .
	/GZIP [= <i>n</i>]	GZIP Compression: Specifies GZIP-compatible stream data compression. /GZIP or /GZIP= <i>n</i> (for nonzero values of <i>n</i>) enables compression on WRITE and decompression on READ. /GZIP=0 disables compression and decompression. Before issuing /GZIP=0 to disable compression and decompression, check the \$ZEOS special variable to make sure that a stream data read is not in progress. /GZIP compression has no effect on I/O translation, such as translation established using /IOTABLE. This is because compression is applied after all other translation (except encryption) and decompression is applied before all other translation (except encryption).
	/COMPRESS= <i>str</i>	Specifies the stream data compression type as one of these values: <ul style="list-style-type: none"> • "zlib" — Use the zlib compression library. /COMPRESS="zlib" is equivalent to /GZIP=1 • "zstd" — Use the Zstandard compression algorithm. • "lz4" — Use the LZ4 compression algorithm. • "deflate" — Use the DEFLATE compression algorithm. <p>To disable compression, specify /COMPRESS=" ". To compress a string, use %SYSTEM.Util.Compress().</p>

10.3.3 OPEN Argument Keywords

The following table describes the **OPEN** command argument keywords for sequential files:

Table 10–2: OPEN Keyword Arguments for Sequential Files

Keyword	Default	Description
/PARAMS= <i>str</i> or /PAR= <i>str</i>	No default	Corresponds to the <i>parameters</i> positional parameter. (It provides a way to specify a parameter letter code string in a position-independent way).
/RECORDSIZE= <i>int</i> or /REC= <i>int</i>	No default	Corresponds to the <i>reclen</i> positional parameter, which establishes a record size for fixed-length records. (Currently only implemented for READ operations.)
/TERMINATOR= <i>str</i> or /TER= <i>str</i>	No default	Corresponds to the <i>terminators</i> positional parameter, which establishes user-defined terminators. <i>str</i> is a string of user-defined record terminators that apply to stream mode only. They let you override the default terminators: carriage return, line feed, and form feed. User-defined terminators only apply to input, they do not affect how data is written to the file (terminators are written to a file as special characters). If there's more than one user-defined terminator, it is treated as a list of terminators, not a multi-character sequence to be used as a single terminator.

10.3.4 OPEN Mode Locking

When two processes attempt to open the same sequential file, the second **OPEN** succeeds or fails based on the mode used by the first **OPEN**. The following tables show the interactions between two opens using exclusive (“L”) and non-exclusive read and write modes. Note that the interpretation of these interactions is platform-dependent. Tables are provided for Windows operating systems and UNIX® operating systems.

In the following tables, the horizontal axes indicates the open mode of the first **OPEN** and the vertical axis indicates the open mode of the second **OPEN**. A 1 indicates that the second **OPEN** succeeds; a 0 indicates that the second **OPEN** fails.

Table 10–3: Windows OPEN Mode Interactions

	W	RW	RL	WL	RWL	R
W	1	1	1	0	0	1
RW	1	1	1	0	0	1
RL	1	1	1	0	0	1
WL	0	0	0	0	0	0
RWL	0	0	0	0	0	0
R	1	1	1	0	0	1

For Windows systems, the interactions in this table apply equally to concurrent opens from the same InterSystems IRIS instance, concurrent opens from two different InterSystems IRIS instances, or concurrent opens by InterSystems IRIS and a non-InterSystems IRIS application (with restrictions on non-InterSystems IRIS applications, as described below).

Table 10–4: UNIX® OPEN Mode Interactions

	W	RW	RL	WL	RWL	R
W	1	1	1	1	1	1
RW	1	1	1	1	1	1
RL	1	1	1	0	0	1
WL	1	1	0	0	0	1
RWL	1	1	0	0	0	1
R	1	1	1	1	1	1

For UNIX® systems, the interactions in this table only to concurrent opens from the same InterSystems IRIS instance. They do not govern concurrent opens from two different InterSystems IRIS instances, or concurrent opens by InterSystems IRIS and a non-InterSystems IRIS application.

10.3.4.1 Interactions with Non-InterSystems IRIS Software

On Windows systems, opening a sequential file in InterSystems IRIS for “WL” write access generally prevents a non-InterSystems IRIS application from opening the sequential file for write access. Similarly, a non-InterSystems IRIS application opening a sequential file for write access generally prevents an InterSystems IRIS process from concurrent “WL” write access.

However, certain non-InterSystems IRIS applications, including the Notepad and WordPad applications, open a file, make a copy of the file in shared mode, and then immediately close it. Thus an InterSystems IRIS process could still open the file in “WL” mode. An error would occur when one of these non-InterSystems IRIS applications then either attempts to save changes from their copy to the original, or attempts to reopen the original file. A more serious situation can occur as follows: If one of these non-InterSystems IRIS applications opens a file, then InterSystems IRIS opens, modifies, and closes the file, then the non-InterSystems IRIS application saves changes to the file, the changes made by both processes are saved, and the integrity of the file data could be compromised.

On UNIX® systems, opening a sequential file in InterSystems IRIS for “WL” write access generally has no effect on the behavior of non-InterSystems IRIS applications. You must use locks to reliably restrict write access from non-InterSystems IRIS applications.

10.3.5 Examples

The following example opens the file “LUDWIG.B” in the current directory. Because it specifies no mode parameters, it opens the file with read access and in stream mode by default:

ObjectScript

```
OPEN "LUDWIG.B"
```

The following example opens a new file “LIST.FILE” in the current directory, with write access, in stream format. Notice that you do not need parentheses when you include only the first of the arguments they would normally enclose.

ObjectScript

```
OPEN "LIST.FILE" : "WNS"
```

The following example opens a file “CARDS” in the current directory, with read and write access, and 80-character fixed-length records.

ObjectScript

```
OPEN "CARDS" : ( "FRW" : 80 )
```

The following example opens the stream-format file “STRNG” in the directory c:\usr\dir, with non-default terminators.

ObjectScript

```
OPEN "c:\usr\dir\STRNG" : ( "S" : : $CHAR(0) _ $CHAR(255) )
```

10.4 USE Command

The **USE** command makes an opened sequential file the current device. You can have many open sequential files, but you can *use* only one sequential file at a time.

10.4.1 Syntax

```
USE file:position
```

where

file

Any valid [file specification](#), enclosed in quotation marks. The specified file must already have been opened. In UNIX pathnames, you can use tilde (~) expansion to indicate the current user’s home directory. For example: ~myfile or ~/myfile.

position

Optional — The position of the next **READ** or **WRITE** within the file. The *position* value is a numerical expression whose meaning depends on the record format of the file. For fixed-length records, *position* is the absolute record number, relative to zero, where each record contains the number of characters specified in the previous **OPEN** command. For stream or variable-length records, *position* is the absolute byte position relative to zero. The default is to read or write records sequentially from the beginning of the file.

You can use the [\\$ZSEEK](#) function to set the file position, specified by character count offset from the beginning, current position, or end of the sequential file. The [\\$ZPOS](#) special variable contains the current character count position from the beginning of the sequential file.

10.4.2 USE-Only Command Keywords

In addition to the command keywords that it shares with **OPEN**, listed above, the **USE** command has its own set of keywords:

Table 10–5: USE-Only Command Keywords for Sequential Files

Keyword	Default	Description
/POSITION= <i>n</i>	Current file position. (The file pointer position is at the beginning of a file when it is first opened, unless the file was opened in append mode. In that case, the file pointer position is at the end of the file.)	Corresponds to the positional parameter, which sets the position of the next READ or WRITE within a file.

10.5 READ Command

After a positioned **READ** or **WRITE**, subsequent **READ** or **WRITE** operations proceed sequentially until the next **USE** command with a position parameter.

The **READ** command reads data from the current device, one record at a time. Reading past the end of file causes an <ENDOFFILE> error.

10.5.1 Syntax

```
READ x#n:timeout
```

where

x

The variable that will hold the record read from the file.

n

Optional — For a variable-length read, the number of characters to read, specified as an integer. For a fixed-length read, this argument is ignored.

timeout

Optional — The number of seconds to wait for the read operation to complete before timing out. Either an integer value or a variable that resolves to an integer.

The *timeout* argument, though optional, is strongly recommended because the success or failure of the **READ** is indicated by the value of the **\$TEST** special variable if *timeout* is specified. **\$TEST** is set to 1 if the read attempt succeeds before the timeout expires; if the timeout expires, **\$TEST** is set to 0.

The following example shows a **READ** operation reading fixed-length records from a Windows sequential file. It creates a sequential file, writes data into it, then closes the file. It then opens this file for fixed-length reads of 4 characters ("RF" : 4). It sets the **USE** position argument to the first record (record 0); each read operation advances this position. A **FOR** loop reads each four-character record into a subscripted variable. The **ZWRITE** command then displays all of these subscripted local variables and their values.

ObjectScript

```
SET myf="C:\InterSystems\IRIS\mgr\temp\myfixedlengthfile"
OPEN myf:("NW") USE myf WRITE "ABCDEFGHIJKLMNQRSTUWXYZ"
CLOSE myf
OPEN myf:("RF":4) USE myf:0 FOR i=1:1:7 {READ x(i):5}
CLOSE myf
ZWRITE
```

10.5.2 Example

The following example reads the third, fourth, and fifth records of a fixed-length file:

ObjectScript

```
SET myfile="FIXED.LEN"
OPEN myfile:("FR":100)
USE myfile:2
READ var1(3),var1(4),var1(5)
```

10.6 WRITE Command

After a positioned **READ** or **WRITE**, subsequent **READ** or **WRITE** operations proceed sequentially until the next **USE** command with a position parameter.

The **WRITE** command writes data, one record at a time, to the sequential file that is the current device.

10.6.1 Syntax

```
WRITE x
```

where

x

The data in variable *x* is written as one record in the sequential file.

10.7 CLOSE Command

The **CLOSE** command relinquishes ownership of a sequential file.

If the specified file is not open or does not exist, InterSystems IRIS ignores **CLOSE** and returns without issuing an error.

10.7.1 Syntax

```
CLOSE file
CLOSE file:"D"
CLOSE file:("R":newname)
```

where:

file

Any valid [file specification](#), enclosed in quotation marks. The specified file must already have been opened. In UNIX pathnames, you can use tilde (~) expansion to indicate the current user's home directory. For example: ~myfile or ~/myfile.

"D"

Closes and deletes the file with the name specified in the argument.

("R":*newname*)

Closes the file with the name specified in the argument and renames it *newname*.

10.7.2 CLOSE-Only Command Keywords

The following table describes the keywords for controlling sequential files with only the **CLOSE** command.

Table 10–6: CLOSE-Only Command Keywords for Sequential Files

Keyword	Default	Description
<code>/DELETE[=<i>n</i>]</code> <i>or</i> <code>/DEL[=<i>n</i>]</code>	0, unless the file was marked for delete when it was opened.	Corresponds to the D parameter code, which specifies that the file should be deleted. <code>/DELETE</code> or <code>/DELETE=<i>n</i></code> for nonzero values of <i>n</i> enable the parameter code and <code>/DELETE=<i>n</i></code> for a zero value of <i>n</i> disables the parameter code.
<code>/RENAME=<i>name</i></code> <i>or</i> <code>/REN=<i>name</i></code>	Do not rename the file.	Corresponds to the R parameter code and the file name positional parameter. The R parameter code specifies that the file should be renamed and the file name positional parameter gives the new name of the file.

11

Spool Device

This page discusses spooling in InterSystems IRIS® data platform.

11.1 Introduction

InterSystems IRIS® data platform enables you to send print output directly to your printer or screen, or retain it in a spool global for printing at a later time. InterSystems IRIS spooling is independent of the spooling performed by your operating system.

Spooling in InterSystems IRIS is a technique that lets you automatically save the output of a program in the ^SPOOL sub-scripted global instead of printing it immediately. You can print the output later by sending the contents of the ^SPOOL global to the printer. This page describes two ways of using this spooling facility: using ObjectScript commands (**OPEN**, **USE**, **WRITE**, **CLOSE**), or using the **%IS** and **%SPOOL** utilities.

11.2 Opening and Using the Spool Device

To send output to the spool global in your current namespace, you open the spooler and specify it as your output device.

The spooler is a predefined device provided with InterSystems IRIS. It is assigned device number 2 in the device table. This device number can be used to identify the spooler device in **OPEN**, **USE**, and **CLOSE** commands.

You can access spooler device information through the Management Portal. Select **System Administration, Configuration, Device Settings, Devices**. Here you will find both device 2 and a device named SPOOL. By default, these are both mapped to the same physical device (device 2) and have the same option values.

When you set the InterSystems IRIS spooler as the current device, InterSystems IRIS stores any output sent to Device 2 in the global ^SPOOL in your current namespace. Each line in ^SPOOL is in a separate global node.

There are two ways to open the InterSystems IRIS spooler and set it as the current output device:

- Issue **OPEN** and **USE** commands
- Invoke the [%IS utility](#)

11.2.1 OPEN and USE Commands for Spooling Device

You can open the spooling device directly by issuing **OPEN** and **USE** commands to that device.

```
OPEN 2:(doc_num:index) USE 2
```

Table 11–1: OPEN Positional Parameters for Spooling

Parameter	Definition
<i>doc_num</i>	The number of the spool document (file) you want to open. Spool documents are stored in the ^SPOOL global. The default is 1.
<i>index</i>	Line number, 1 or greater, within the spool document. The default is 1.

These are positional parameters. If you omit both parameters, they default to (1:1). You can set first parameter (*doc_num*) and omit the second (*index*), which defaults to 1. However, if you set the second parameter, you should specify the first parameter.

InterSystems IRIS uses these values to locate the lines you want to print. It treats the *doc_num* parameter as the first subscript of the ^SPOOL global. It treats the *index* parameter as the second subscript of the ^SPOOL global.

11.2.1.1 USE Command

When you issue **USE 2** for device 2 after the command `OPEN 2:(doc_num:index)`, InterSystems IRIS sends any subsequent output to the spooler at `^SPOOL(doc_num:index)`. Each output line is stored as a separate global node within ^SPOOL.

11.2.1.2 WRITE Command

To write a line to the ^SPOOL global, issue a **WRITE** command, ending with a line terminator character. For example:

ObjectScript

```
/* Writing to the ^SPOOL global */
OPEN 2
USE 2
  WRITE "First line of text",!
  WRITE "Second line of text",!
CLOSE 2

/* Displaying the ^SPOOL global */
WRITE ^SPOOL(1,1),^SPOOL(1,2)
```

Each line ends with a line terminator (the exclamation mark) and is stored in a separate global node.

However, in producing a single print line, you may want to use several **WRITE** commands; if a **WRITE** does not contain a line terminator character, the next **WRITE** command appends to the same print line. Both write to the same global node. This line is held in a buffer and not written into the spool global until either a line termination character is issued, or the spooler device is closed.

The following example writes one global node when **CLOSE** is issued:

ObjectScript

```

/* Writing to the ^SPOOL global */
OPEN 2
USE 2
    WRITE "First half of line "
    WRITE "Second half of line"
CLOSE 2

/* Displaying the ^SPOOL global */
WRITE ^SPOOL(1,1)

```

The line terminator character is commonly the ! (exclamation mark) **WRITE** command code character. This is equivalent to a carriage return (ASCII 13) *and* a line feed (ASCII 10). To terminate a line, both of these control characters are necessary. Issuing just a carriage return (ASCII 13) causes the carriage return to be concatenated into the line node, rather than initiating a new line node. In the Terminal, a line of this type displays as an overwrite of the text before the carriage return, by the text following it.

The following example writes only two line nodes in the ^SPOOL file:

ObjectScript

```

/* Writing to the ^SPOOL global */
OPEN 2
USE 2
    WRITE "AAAAAAAAAA", $CHAR(10), $CHAR(13)
    WRITE "BBBBBBBBBB", $CHAR(13)
    WRITE "XXXX", !
CLOSE 2

/* Displaying the ^SPOOL global */
WRITE ^SPOOL(1,1), ^SPOOL(1,2)

```

For more information, see the [OPEN](#), [USE](#), [WRITE](#), and [CLOSE](#) commands in the *ObjectScript Language Reference*.

11.3 Spooling and Special Variables

When writing to ^SPOOL, InterSystems IRIS continually updates the **\$X** and **\$Y** special variables. **\$X** indicates the number of characters written to the current index line, and **\$Y** contains the number of lines written during the current **OPEN**. Note that the value of **\$Y** is not necessarily the same as the node index. For example:

ObjectScript

```

/* Writing to the ^SPOOL global */
OPEN 2:(2:3)
USE 2
    WRITE "Hello " SET x1=$X,y1=$Y,z1=$ZA
    WRITE "world", ! SET x2=$X,y2=$Y,z2=$ZA
    WRITE "Good to see you", ! SET x3=$X,y3=$Y,z3=$ZA
CLOSE 2

/* Displaying the ^SPOOL global */
WRITE ^SPOOL(2,3), ^SPOOL(2,4)
WRITE !, "$X=", x1, " ", x2, " ", x3
WRITE !, "$Y=", y1, " ", y2, " ", y3
WRITE !, "$ZA=", z1, " ", z2, " ", z3

```

In this example, the first **WRITE** sets **\$X=6** (the current column number) and the second and third **WRITE** both set **\$X=0** (because of the line returns). The first **WRITE** sets **\$Y=0**, the second **\$Y=1** (because of the line return), and the third **\$Y=2**. Note however, that the lines that are being written are ^SPOOL(2,3), and ^SPOOL(2,4). To determine the index number, use **\$ZA**.

Writing to a spool file sets the **\$ZA** special variable with the next available index number. Thus, if you are writing to `index=3`, and do not include a line terminator, **\$ZA=3** (because the next **WRITE** continues writing to index 3), but if you do include a line terminator, **\$ZA=4**.

The **USE** command sets **\$ZB** to contain the `doc_num` of the spool file specified in the **OPEN** command.

Note: The **\$IO** special variable is not modified by writing to a spool file. Normally, **\$IO** is reset by a **USE** command to contain the ID of the current device. However, when the device is an output-only device (such as the spooler), **\$IO** continues to contain the ID of the current *input* device.

For more information, see the **\$X**, **\$Y**, **\$ZA**, **\$ZB**, and **\$IO** special variables in the *ObjectScript Language Reference*.

11.4 Closing the Spool Device

When you issue **CLOSE** for device 2, the system automatically sets the node `^SPOOL(doc_num, 2147483647)` to store information about closing the spool document and the highest index number the output reaches.

11.4.1 Changing Namespaces

When you change namespaces with a **SPOOL** device left open, the spool device is closed automatically before the namespace change takes effect. The closing record in the `^SPOOL` global is written into the correct database.

11.4.2 Abort Job Processing

If you open a spool device, dismount the current directory, then issue a **HALT** command or the **Terminate(\$JOB)** method of the `SYS.Process` class, InterSystems IRIS returns a persistent `<PROTECT>` error for subsequent attempts to access this spool device. To avoid this, change the namespace to automatically closes any open **SPOOL** device.

11.5 Viewing the ^SPOOL Global

Like any subscripted global, you can display lines from the spool file by issuing a **WRITE** command, as follows:

ObjectScript

```
WRITE "1st spool file node: ", ^SPOOL(1,1), !
```

However, to view and edit the spool file itself, go to the Management Portal and select **System Explorer, Globals**. Select your current namespace, locate the **SPOOL** global, then click **data**. This displays spool file data similar to the following examples.

In the following spool file, the (!) termination character ends each node line in the spool file. These termination characters are part of the spool file, concatenated to the text string as a `$CHAR(13,10)` (Return and Line Feed).

```
^SPOOL(1,1)=<<"First line of text"_$C(13,10)>>
^SPOOL(1,2)=<<"Second line of text"_$C(13,10)>>
^SPOOL(1, 2147483647)={59605, 43605{3{
```

In the following spool file, there are no line termination characters. The two **WRITE** commands wrote a single node line, which was terminated by the closing the spool file.

```
^SPOOL(1,1)=First half of line Second half of line
^SPOOL(1, 2147483647)={59605, 43725{2{
```

In the following spool file, return and line feed characters were explicitly coded in the **WRITE** commands. The \$CHAR(10) line feed character initiates a new node line, and the \$CHAR(13) return character is concatenated into these node lines.

```
^SPOOL(1,1)=<<"AAAAAAAAAA"_$C(10)>>
^SPOOL(1,2)=<<$C(13)_"BBBBBBBBB"_$C(13)_"XXXX"_$C(13,10)>>
^SPOOL(1,2147483647)={59605,44993}{3{
```

The final line of the spool file is generated by InterSystems IRIS when you close the spool file. It consists of the literal 1,2147483647; the date and time in \$HOROLOG format (59605,44993), and the number of lines in the spool file, including the final line.

You can edit or delete these spool file text lines. using the **data** display for the SPOOL global in the Management Portal **System Explorer, Globals** option.

11.6 Opening the Spooler Using the %IS Utility

%IS provides a convenient user interface at which a user can select the spool device, as well as any other device defined in the ^%IS global in the %SYS namespace. Using **%IS**, you can create a named spool file and write lines of text to that file. You can then print this spool file using the [%SPOOL utility](#).

Note: Only spool files opened using the **%IS** utility can be manipulated using the **%SPOOL** utility.

To create a spool file using **%IS** do the following steps:

1. Invoke the **%IS** utility to open the spooler:

```
>DO ^%IS
```

2. At the “Device” prompt enter “2” or the mnemonic “SPOOL”.
3. At the “Name” prompt, enter the name of the spool document (file). (Press **Enter** at the “Name” prompt if you decide not to open the spool device.) If you enter the name of an existing spool document, **%IS** asks if it is correct, displays the last line of the file, and lets you choose where to add the new information. If you enter a new name, **%IS** asks if you want to create a new document. Press **Enter** to create a new spool document, or enter “No” to redisplay the “Name” prompt.
4. At the “Description” prompt, enter a one-line description. To increase readability, the description of the spooled document is on a separate line and wraps at column 70 if it is too long to fit on one line.

The following example writes the line “TESTING SPOOL FUNCTIONALITY” to the ^SPOOL global. *IO* is a variable that **%IS** sets to the device you specify at the “Device” prompt.

```
%SYS>DO ^%IS
Device: 2
Name: SPOOLFILE not found
Create new document 'SPOOLFILE'? Yes => <RETURN>
Description: This is my test spool file
%SYS>USE IO WRITE "TESTING SPOOLING FUNCTIONALITY",!
%SYS>CLOSE IO
```

11.7 Managing Spooled Documents Using %SPOOL

You manage spool files created when you access the InterSystems IRIS spool device with the **%SPOOL** utility. InterSystems IRIS spooling is independent from system spooling.

Spooling in InterSystems IRIS is a technique that lets you automatically save the output of a program in the global ^SPOOL instead of printing it immediately. You can print the output later by sending the contents of the global to the printer.

Use the **%SPOOL** utility to print, list, or delete spool documents in the ^SPOOL global in your current namespace. If you send a document to the spooler from a particular namespace, you must run the **%SPOOL** utility from that namespace to access it.

Note: Only spool files opened using the **%IS** utility can be manipulated using the **%SPOOL** utility.

%SPOOL asks which spooling option you want. You can choose any of the three functions by entering either:

- The menu number of the function
- The first letter of the function name

You can also enter a question mark (?) to display a list of these functions.

The following example shows how you select a spooling function, in this case, Print.

```
%SYS>DO ^%SPOOL
Spool function: ?
The available spool functions are:
  1) Print
  2) List documents
  3) Delete document
Enter the number or first few characters of the name of the
spool function you want.
Spool function: 1 Print
```

The following sections describe how to use the **%SPOOL** utility to perform the following tasks:

- Print spool documents
- List spool documents
- Delete spool documents

11.7.1 Printing with %SPOOL

Option 1 of the **%SPOOL** utility menu, Print, lets you print one or more documents in the ^SPOOL global on any device, resume printing an interrupted document, and handfeed single sheets of paper into a letter-quality printer. By sending output to the spooler, you release your terminal for other uses while the output device prints your document.

You can start printing either before or after the spool document is fully created. If the printer catches up to the new output, the print process pauses for five seconds, then prints all the output accumulated during that time. The print process knows when you have closed the spool document and finishes when the document is done.

As **%SPOOL** prints the document, it keeps track of the pages it has printed. It also creates a page index, so that you can sort through the document by page number and begin printing at the top of any page you choose.

If you stop printing (for example, by pressing **ctrl-c** during terminal output, or if your printer breaks), you can later resume at the top of the last partially printed page or at the top of any other page in the document. Note that InterSystems IRIS does not count form feeds at the start of the document as pages in the page count.

%SPOOL uses the term *despool* to mean print. There will be values in the Despool start-end column and on the description line only if the document has been printed (despooled).

11.7.1.1 Using the Print Function

1. At the “Spool function:” prompt, enter 1.
2. At the “Name:” prompt, enter a ? to display help text, enter ?? to list all existing spool documents in the current namespace, or enter the name of the spool document you want to print. %SPOOL confirms that this is the correct document.
3. When %SPOOL asks you for the page where you want to start printing, press **return** to start at the first page, or enter any page number in the document. If you try to start printing at the top of a page the printing process has not yet reached, the following message displays: **WARNING: Printing hasn't reached this point.** After this warning, %SPOOL asks if you are sure you want to start printing on the page you selected. If you enter No, it returns you to the “ Start at page:” prompt. If you enter Yes to confirm the starting page, %SPOOL displays the first few lines of the page in question and reconfirms that this is the right page.
4. You are prompted for the number of copies.
5. %SPOOL lets you enter the names of other spool documents you want to print. When you respond to the “ Name:” prompt by pressing **return**, it asks you for the output device and its right margin. Enter this information to start printing. Note that %SPOOL issues a form feed after each page, whether you are printing on a screen or a printer.

The following example shows you how to print a document in the ^SPOOL global, in this case called SPOOLFILE. The document will print on the device called MYPRINTER.

```
%SYS>DO ^%SPOOL

Spool function: 1 Print
Name: ??

# Name          Lines  Spool start      Despool start-end
1 SPOOLFILE     1      30 Aug  2:23 pm    30 Aug  2:25 pm-2:25 pm
  This is my test spool file

Name: SPOOLFILE

1 SPOOLFILE     30 Aug 2003  2:23 pm  this is my test spool file
SPOOLFILE has 1 pages.
Is this correct? Yes=>Y
Start at page: 1=>Y
How many copies? 1=>Y

Name:RETURN
Print spooled files on
Device: MYPRINTER RETURN Parameters: "WNS"=>
Free this terminal? Yes =>Y
Starting Job in background . . . started.

Spool function:
```

11.7.2 Listing Spooled Documents

Option 2 of the %SPOOL utility menu, List documents, displays a list of the documents currently spooled for the directory in which %SPOOL is running. If there is no Despool start-end value, the document has not yet been despoiled (printed).

The description of each spooled document appears on one or more separate lines following the rest of the information about that document.

In the following example, the user selected Option 2. The display reveals two documents stored in the spooler. The first was stored on August 30 at 2:23 p.m. and printed the same day at 2:25 p.m. The second was stored on March 4 at 11:39 a.m. and printed the same day at 11:42 a.m.

```
Spool function: 2   List documents
# Name      Lines   Spool start      Despool start-end
1 SPOOLFILE 1     30 Aug 2:23 pm   30 Aug 2:25 pm- 2:25 pm
  This is my test spool file

3 LONGFILE  1     04 Mar 11:39 am  04 Mar 11:42 am- 11:42 am
  This is a very long description line that shows you what happens when you
  have a long description. It shows you how the text wraps from line to line.
  This particular description was made intentionally long, so as to wrap at least
  twice.
```

11.7.3 Deleting Spooled Documents

Option 3 of the **%SPOOL** utility menu, Delete document, lets you delete one or more spool documents. When **%SPOOL** prompts you for a name, enter the name of the document you want to delete, or enter ?? to display the current spool documents for the namespace you are in. Enter a ? for help text.

%SPOOL confirms that this is the correct document, and that you want to delete it. If you answer “Yes,” **%SPOOL** deletes the document, and allows you to name other documents you want to delete.

The following example deletes the spooled document called SPOOLFILE.

```
Spool function: 3   Delete document
Name: ??

# Name      Lines   Spool start      Despool start-end
1 SPOOLFILE 1     30 Aug 2:23 pm   30 Aug 2:25 pm- 2:25 pm
  This is my test spool file

Name: SPOOLFILE

1 SPOOLFILE    30 Aug 2003  2:23 pm  this is my test spool file
SPOOLFILE has 1 pages.
Is this correct? Yes=>Y
Delete SPOOLFILE? No=> Y [Deleted]

Name:
```

12

Printers

This page discusses how to configure and use print devices in InterSystems IRIS® data platform. A printer is a physical output-only device. A printer may be a character printer, or a non-character device such as a fax or plotter.

In most cases, output is not sent directly to a printer. Often, output to be printed is first sent to a logical spool device (the ^SPOOL global). The contents of the ^SPOOL global can then be sent to the physical printer. For further details on spooling, see [Spool Device](#).

12.1 Overview of Printers

Note that Windows and UNIX® handle printer I/O differently.

- Windows systems handle a printer as a sequential I/O device, and thus follows the same syntax as sequential file I/O. However, a printer connected through a serial communications port is handled as a terminal I/O device.
- UNIX® systems always handle a printer as a terminal I/O device. UNIX® treats it as a “character special” file on a tty device, and thus follows the same syntax as terminal I/O.

On a Windows system, you can return a count of the current printers on your system using the `%Library.Device.InstalledPrinters()` method. You can return a list of the current printers on your system using the `%Library.Device.GetPrinters()` method.

12.2 Specifying a Printer

A printer can be assigned a device number between 256 and 2047, inclusive. This range of device numbers are also used for terminals and flat files.

On a Windows system, you can refer to a printer using its device number or an assigned device mnemonic. The Windows default printer mnemonic is `|PRN|`.

There are two ways to specify a printer:

- Call the `%IS` utility, which allows you to specify the device by using a mnemonic defined in the `%IS` global. This utility opens the device and sets its parameters.
- Issue the I/O commands **OPEN**, **USE**, and **CLOSE**, using the operating system device name, specified as a quoted string.

12.2.1 Opening a Printer

When opening a printer, you can use the device name to specify the device. The device name must be enclosed in quotes. The maximum length of this device name is 256 characters. The form is as follows:

```
OPEN "device"
USE "device"
CLOSE "device"
```

On Windows, you can also have a printer attached to a serial communications port. In this case, the printer is treated the same as terminal I/O with the following syntax:

```
OPEN "comn:"
```

Where *n* is the port number to which the printer is attached.

12.2.2 Specifying a Printer on Windows

To use the default printer on Windows, enter the following:

ObjectScript

```
OPEN "|PRN|"
```

This causes InterSystems IRIS to use the default Windows printer for your machine, if you have set the default printer for your machine. (For information on how to set the default printer, see your Windows documentation.)

To use a printer other than the default printer, enter the following:

ObjectScript

```
OPEN "|PRN|printer"
```

Parameter	Description
<i>printer</i>	The Universal Naming Convention (UNC) name or a name that shows up on your machine's list of printers.

The following example illustrates the use of a UNC name:

ObjectScript

```
OPEN "|PRN|\\business\accounting"
```

The following example illustrates the use of a non-UNC name that might appear on your machine's list of printers:

ObjectScript

```
OPEN "|PRN|HP LaserJet 5P"
```

Note: InterSystems discourages the use of printer port names like COM1, LPT1, etc. If you do use such a name, InterSystems IRIS will try to figure out which printer, if any, that name refers to and then it will use that name. However, this will be a slow operation and is not really appropriate for Windows.

On Windows systems, a printer is identified by the name on the **OPEN** command and is handled by the sequential I/O module, not the terminal I/O module. Thus the **OPEN** and **USE** command arguments supported are the same as those for

sequential file I/O, *not* terminal I/O. The exception to this is a printer connected to a Windows system through a serial communications port; in this case, the printer is handled as a terminal I/O device.

On Windows systems, you cannot use the “:n” positional parameter to control the print margin used. Such notation is ignored by InterSystems IRIS. Code such as “|PRN|”:121 is ignored. To control the printer width, send the appropriate control characters for that printer. The notation does work on other platforms.

On Windows, **OPEN** supports most of the sequential I/O keyword parameters, as described in [Sequential File I/O](#). The following table describes additional printer keyword parameters for controlling a printer (handled as a sequential file) on Windows systems with the **OPEN** command.

Table 12–1: Additional OPEN Keyword Parameters for Windows Printers

Keyword	Default	Description
/DOCNAME= “name”	“IRIS”	/DOCNAME enables you to redefine the printer job name.
/OUTPUTFILE= “filename”	NULL	/OUTPUTFILE redirects print to a file. Specify a fully-qualified pathname .
/DATATYPE= “type”	“RAW”	/DATATYPE enables you to redefine the datatype of the printer spool data. One frequently-used datatype is TEXT.

On Windows systems, if the **OPEN** prints directly to the printer (does not use a logical spool device), the **OPEN** command *timeout* argument does not expire if the printer is turned off or does not exist. The InterSystems IRIS process remains in a suspended state until the printer becomes available, or until the print document is cancelled from the Windows Control Panel.

12.2.3 Specifying a Printer on UNIX®

To open an I/O device on a terminal that has the UNIX® device name `/dev/tty06`, enter the following command

ObjectScript

```
OPEN "/dev/tty06"
```

On UNIX® systems, a printer is identified by the name on the **OPEN** command and is handled as a “character special” file on a tty device. Thus the **OPEN** and **USE** command arguments supported are the same as those for terminal I/O, *not* sequential file I/O.

On UNIX®, **OPEN** supports most of the terminal I/O keyword parameters, as described in [Terminal I/O](#).

12.3 Directing Output to a Printer

You can use the %IS utility to direct output to a printer. You can invoke the %IS utility with the command `DO ^%IS`. (You can also use `DO OUT^%IS` to specify that you are selecting an output-only device.) In either case, InterSystems IRIS returns the `Device:` prompt. To specify a printer, reply with either the default mnemonic “|PRN|”, or the mnemonic of another configured printer. The %IS utility then suggests OPEN parameters; for a printer, the default is “W” (write-only). You can accept the parameter default by pressing **Enter**, as shown in the following example:

```
%SYS>DO ^%IS
Device: |PRN|
Parameters? "W" => <RETURN>
%SYS>
```

This opens the specified printer as an output device for the current process.

The %IS utility sets various variables. The following are the printer default values on a Windows system.

Table 12–2: Variables Set by %IS

Variable	Value	Description
IO	PRN	Device mnemonic of selected device.
IOF	#	Form feed character. <code>WRITE #</code> issues a form feed and changes \$Y . <code>WRITE @IOF</code> should be used to form feed.
IOBS	\$C(8)	Backspace/overprint character (ASCII 8). <code>WRITE \$CHAR(8)</code> issues a backspace and changes \$X . <code>WRITE *8</code> issues a backspace but does not change \$X . <code>WRITE @IOBS</code> should be used to backspace.
IOM	132	Right margin; line length in characters.
IOSL	66	Page length in characters.
IOT	OTH	Device type. Here “Other”.
IOST	P-DEC	Device subtype name.
IOPAR	("W")	OPEN parameters. Here “W” because a printer is a write-only device.
MSYS	M/WNT	Type of system (such as UNIX® or Windows). M/WNT is InterSystems IRIS on Windows.
POP	0	Indicates that %IS was run (and these variables initialized). If 0, a device was specified. If 1, no device was specified (user entered STOP in response to the <code>Device:</code> prompt).

Most of these values can also be viewed and set from the Management Portal. Select **System Administration, Configuration, Device Settings**. View the current contents of **Devices** and **Device Subtypes**. Select **Edit** to view the settings for a specific printer.

12.3.1 %IS Printer Set-Up Variable

When you call %IS for spooling, you can pass it the IOPGM variable, which specifies the name of the routine that sets up printer forms alignment.

12.4 Printer as Alternate Device

You can specify a printer as the alternate device for all processes by defining a new device named “A” and specifying a physical device of |PRN|. Then when you use %IS, specify A at the `Device:` prompt.

You can set a printer as the alternative I/O device for a terminal process. Go to the Management Portal. Select **System Administration, Configuration, Device Settings, Devices**. Select **Edit** for the current terminal device and specify an Alternate Device value.

13

Controlling Devices with Mnemonic Spaces

A mnemonic space is an InterSystems IRIS routine that performs device control actions, such as cursor movement and device attributes. Each action is associated with a label. These labels are the mnemonics used in the **WRITE** /mnemonic command. For more information on the **WRITE** /mnemonic syntax, see the **WRITE** command description for each device type in the other pages in this document.

13.1 Predefined Mnemonic Spaces

InterSystems IRIS provides predefined mnemonic spaces described in the table below.

Table 13–1: Predefined Mnemonic Spaces

Routine Name	Device Type Default	Description
^%X364	Terminals, Sequential files, Other devices	Mnemonic space for X3.64 (ANSI) terminals. For information, see Mnemonic Space for X3.64 .
^%XDTM	DTM PC Console	Mnemonic space for DTM PC Console. For information, see Mnemonic Space for DTM PC Console .

13.2 Setting Up Default Mnemonic Spaces

You can change the mnemonic space that is a default for the following device types in the Management Portal. Select **System Administration, Configuration, Device Settings, IO Settings**. This displays the mnemonics for the following:

- Terminals
- Sequential files
- Other

After a default mnemonic space is defined, the control mnemonics in the default mnemonic space for the current device are used if a `WRITE /mnemonic` command is issued, unless the default mnemonic space is overridden by a `mnespace` argument to the **OPEN** or **USE** command for the current device.

13.3 Creating a Mnemonic Space

You can create your own mnemonic space routines. For example, you might want to create your own for terminal I/O.

1. Create an InterSystems IRIS routine containing the control mnemonics you want. Keep in mind the following points about your routine:
 - The entry points in this routine must be uppercase. These entry points are the mnemonics you reference in **WRITE /mnemonic** commands.
 - Some entry points may require arguments. The code in the mnemonic space at an entry point performs an action on the current device.
 - Cursor movement routines do not move the cursor past the edge of the screen in any direction, nor do they wrap the cursor.
2. To make this mnemonic space available to all users, give the InterSystems IRIS routine a name that begins with % and put it in the %SYS namespace.

13.4 Select a Mnemonic Space

Before you issue `WRITE /mnemonic` commands to a device, you decide whether you want to use the default mnemonic space for the device type as specified in the Management Portal configuration setting.

- When using the default mnemonic space, do not include a `mnespace` parameter when you issue **OPEN** or **USE** commands for the device.
- To use another mnemonic space, specify its name in the `mnespace` parameter of the **OPEN** or **USE** command you issue for the device.

ObjectScript

```
USE "device"::"^%X364"
```

For information on using the `mnespace` parameter, see the [OPEN](#) command and the [USE](#) command, as well as the pages on individual device types.

14

Managing Devices and Mnemonic Spaces

14.1 Device Management Utilities

The table below summarizes the utilities for managing devices.

Table 14–1: InterSystems IRIS Device Utilities

Action	Utility	Description
Define devices	Device configuration in the Management Portal	Allows you to define devices that users can access with the ^%IS utility. The devices are stored in the ^%IS global. You can edit and delete these device definitions. At the Devices subsection, you define devices, including mnemonics and aliases. Default devices are provided. In the Device Sub-Types subsection, you define device subtypes. Default subtypes are provided.
Define default mnemonic spaces	IO configuration options in the Management Portal	You can control devices with the WRITE /mnemonic command. On this panel, you enter the name of the default mnemonic spaces that InterSystems IRIS uses when executing a WRITE /mnemonic command that wasn't preceded by an OPEN or USE command with a mnemonic space specification argument.
Allow users to select a device interactively in character-based applications.	^%IS routine	See Allowing Users to Specify a Device (^%IS) .
Allow users to store print output in a spool file	^%IS and ^%SPOOL routines	See SPOOL Device .

14.2 Default Devices

14.2.1 Devices

When you install InterSystems IRIS, default devices are defined. These are displayed in the **Devices** configuration subsection of the Management Portal. Select **System Administration, Configuration, Device Settings, Devices**. View the list of defined devices.

14.2.2 Device Subtypes

InterSystems IRIS ships with many default *device subtypes*. Each device subtype defines device characteristics, such as screen length and form-feed characteristics.

The complete list of subtypes is in the **Device Subtypes** configuration option of the Management Portal. Select **System Administration, Configuration, Device Settings, Device Subtypes**. View the list of defined subtypes.

14.3 Identifying Devices

When you define a device in the **Devices** configuration section of the Management Portal, you provide three *device identifiers* to specify a device:

- *Mnemonic*, which is used at the `^%IS` Device prompt.
- *Device ID*, which is used in an **OPEN** command.
- *Alias*, which can be used in place of a Device ID in an **OPEN** command.

These device identifiers have several advantages over physical device names:

- They uniquely identify logical devices regardless of how many physical devices you have.
- They assign different characteristics to each logical device.
- They allow user applications to reference devices by consistent numbers without having to know the actual physical device names, which may vary on different platforms.

For more information about using device identifiers, see [Accessing Devices](#).

14.3.1 Device Mnemonics

You can associate one or more *mnemonics* with a particular Device. You use a mnemonic in response to the `Device:` prompt issued by the `^%IS` routine.

Mnemonics provide these advantages:

- They are flexible, because you can change where the mnemonic points rather than developers having to change their applications.
- They are easy for users and developers to remember. For instance, you can set up a printer device with the mnemonic `Printer`, or you can set up a Device ID for a file name and give it the mnemonic `FILE`.

14.3.2 Device IDs

You can identify devices by a number or by their operating system name. You use this identifier in **OPEN** commands.

14.3.3 Device Alias

You can define one or more *alias* values for each InterSystems IRIS device you define. When a user specifies an alias in an **OPEN** command, InterSystems IRIS translates it into the Device ID.

The default Device IDs that InterSystems IRIS provides are appropriate for most users. However, some users may want to override these defaults. You can do this by providing an alias as part of the device's configuration settings in the Management Portal.

14.3.4 Default Device IDs and Mnemonics

When you install InterSystems IRIS, these are the default device numbers and mnemonics for each type of device.

Table 14–2: Default Device Numbers and Mnemonics

Device	Device ID	Mnemonic	Notes
Principal	0	TERM	You cannot change the Device ID for this device.
Spooler	2	SPOOL	

However, InterSystems IRIS also recognizes other device numbers that you can use to define devices. The following table lists the recognized default device numbers.

Table 14–3: InterSystems IRIS Default Device Numbers

Device Number	Type	Definition
0	Principal device	For an interactive process, this is the terminal on which the user logs in. For an InterSystems IRIS jobbed process, this is the null device (by default) or the device provided in the argument list for the job command which creates the jobbed process.
1	messages.log	Use this device number to send error messages or other special messages to the system messages log. For example, issuing the following from a Terminal writes the specified string to the messages log: <code>OPEN 1 USE 1 WRITE "This is a test" CLOSE 1</code> . See also the WriteToConsoleLog() method.
2	InterSystems IRIS system spooler	This is a global that stores output so you can direct it to a physical I/O device at another time.
63	View buffer	Used with the VIEW command and \$VIEW function to transfer data between memory and disk.
20-46, 200-223	Routine interlock devices	Provided for compatibility with DSM locking applications.

Device Number	Type	Definition
4-19, 64-199, 224-255, 2048-2375	IJC devices	Interjob communication (IJC) logical devices. Used to transfer information between InterSystems IRIS processes. You can control the availability of these devices. See Communication Between InterSystems IRIS Processes for more information.
None	The Null device	/dev/null: the Null device on NL: the Null device on Used to dispose of output you do not want displayed.
256-2047	Terminals, printers, and flat files.	

Note: * Device 50 has a hardcoded blocksize of 2048.

14.3.5 Device Types

In addition to the mnemonics and device numbers, InterSystems IRIS supports *I/O device types*. Each internal device number belongs to one of these types. The following table shows the device types:

Type	Meaning
TRM	Terminal
SPL	Spooling device
IPC	Interprocess communication device
OTH	Any other device, such as a printer

14.4 Defining Devices

You define, edit, and delete devices in the **Devices** configuration settings of the Management Portal. The information you enter is stored in the `^%IS` global. For more information about this global, see [Structure of ^%IS Global](#).

If you make device changes while InterSystems IRIS is running, you are prompted as to whether you want to activate the changes without restarting InterSystems IRIS. If you agree to activate the changes, the new definitions are made available immediately to users.

14.5 Accessing Devices

On a Windows system, you must use device numbers for interjob communication devices, and routine interlock devices. For terminals and printers, you can use device mnemonics or device numbers you assign.

On a UNIX® system, you can use UNIX® file specifications to refer to files or you can set up device numbers to refer to files.

You can access a device in one of two ways:

- Entering a device mnemonic at the `Device:` prompt in the `^%IS` utility.
- Issuing an **OPEN** command and entering a Device ID or Alias.

14.5.1 Allowing Users to Select Devices with the ^%IS Utility

If you want users of a character-based application to select a device interactively, call the ^%IS utility from the application. You can learn more about the ^%IS utility in [Allowing Users to Specify a Device](#).

To select a device using the ^%IS utility:

1. At the Device: prompt, enter a device mnemonic.

Table 14–4: Predefined Mnemonic Spaces

Mnemonic	Corresponding Device
<ENTER>	Terminal screen
SPOOL	Spooler
2	Spooler
PRN	Default Windows Printer
File name: MYFILE.TXT DEV\$:[TEST]MYFILE.TXT C:\MGR\MYFILE.TXT	File at path specified or, if no path specification, in current directory.

2. Depending on the type of device, you see another prompt:

Table 14–5: Device Utilities

Device	Prompt	Valid Responses
Terminal	Right Margin	A number representing the number of characters per line.
Printer	Right Margin	A number representing the number of characters per line.
Spooler	Name (of file)	A valid file name for the platform, path optional.
File Name	Parameters	A valid parameter list for an OPEN command for the device type.

14.5.2 Accessing Devices with the OPEN Command

You can use an **OPEN** command either in the Terminal or within an ObjectScript application to open a specific device for reading and writing. When you specify the device, you can use its Device ID or its alias.

14.5.3 Interpretation Levels for Devices

Device identifiers you use with ^%IS or an **OPEN** command go through up to three levels of interpretation. Thus, if you enter the mnemonic 47 at the ^%IS Device: prompt, the final device ID that is used may be different. The three levels are described below.

14.5.3.1 Level 1: %IS Utility Level

The first level is used if a device is selected with the `^%IS` utility. Mnemonics in the `^%IS` global can be associated with device numbers. The `^%IS` utility then issues an **OPEN** command to that device number.

14.5.3.2 Level 2: OPEN Command Level

In an **OPEN** command, InterSystems IRIS checks to see if this number exists in the Alias column of the Device panel table. If so, it translates it to the actual device number or name for that device.

Note: Be sure not to define an alias that matches a Device ID but is associated with a different device if you want to access that device by its mnemonic from `^%IS`.

14.6 Defining Default Mnemonic Spaces

Programmers can control devices by using **WRITE** */mnemonic* commands in their applications. For instance, programmers can move the cursor to a specific column in the current line on a terminal device when they use the `%X364` mnemonic space with this command:

ObjectScript

```
WRITE /CHA(column)
```

The action caused by any particular value of mnemonic is determined by the mnemonic space the **WRITE** command is using. A mnemonic space is a routine with entry points (mnemonics) that define device actions and attributes.

The **WRITE** command uses the mnemonic space defined in the **OPEN** or **USE** command for the device. If the **OPEN** or **USE** command includes no mnemonic space argument, then InterSystems IRIS uses the default mnemonic space for the device type.

14.6.1 Predefined Mnemonic Spaces

InterSystems IRIS ships with the predefined (default) mnemonic space `^%X364`. This is the default mnemonic space for `X3.64` (ANSI) terminals. It is the default at startup for terminals, sequential files, and other devices.

These defaults are defined in the Management Portal. Select **System Administration, Configuration, Device Settings, IO Settings**.

If you create your own mnemonic space routine(s), you may want to change the default mnemonic spaces InterSystems IRIS uses for one or more of these device types.

15

Using ^%IS

^%IS is a general device selection utility for character-based applications. You can use the built-in ^%IS utility to allow users to select a device to which to direct I/O operations. Whenever a device is to be selected, the application program should call the ^%IS utility. This utility allows the user to specify the device to be used and the appropriate **OPEN** command parameters, opens the selected device, then returns device-specific information to the calling program. Users enter a mnemonic that has been defined in the ^%IS global. ^%IS relies upon IO configuration defaults established in the Management Portal.

15.1 How ^%IS Works

15.1.1 Device Prompt

When you call the ^%IS utility, InterSystems IRIS prompts for a device name. You respond in one of the following ways:

- Enter the desired device name or ID number.
- Enter a mnemonic for the device.
- Press **Enter** to select the current device.

^%IS responds as follows:

- If you enter a device mnemonic, ^%IS finds the corresponding device in the ^%IS global and opens it.
- If you enter a device name, ^%IS issues an **OPEN** command to that device.
- If the device is an InterSystems IRIS device ID, ^%IS checks the device table to see if that number is remapped to another actual device number. ^%IS then issues an **OPEN** for the device.

See the discussion “Alternate Devices” that is part of [^%IS Mnemonics](#) section below for information about using alternate devices.

15.1.2 Additional Questions

If the device you specify is a terminal, the utility prompts you with a default right margin. Press **Enter** to select that margin or type a different value. If a program later attempts to write past the specified right margin, the operating system inserts a “CR LF” (carriage return and line feed) when the margin is reached. If you select a device other than a terminal, the utility asks other types of secondary questions.

15.1.3 Examples

In the following example, the user presses **Enter** to specify the terminal. The utility prompts for a right margin, suggesting a default value of 80. At the => prompt the user enters 132 as the new margin setting.

```
%SYS>DO ^%IS
Device: <RETURN>
Right margin: 80 => 132
%SYS>
```

15.1.4 ^%IS Sets the Variable IO and Returns Values of Other Variables

When you select a device, ^%IS sets the variable IO to the device name or number used in the **OPEN** command. ^%IS also returns the values of the variables listed in the following table:

Table 15–1: ^%IS Device Variable Values

Variable	Example	Description
%ANS	Yes	Generic dialog answer.
IO	64	Device number or device mnemonic of selected device.
IOF	#	Form feed. WRITE # issues a form feed and changes \$Y . WRITE @IOF should be used to form feed.
IOBS	*8	Backspace. WRITE \$CHAR(8) issues a backspace and changes \$X . WRITE *8 issues a backspace but does not change \$X . WRITE @IOBS should be used to backspace.
IOM	80	Right margin.
IOSL	66	Screen/page length.
IOT	TRM	Device type.
IOST	C-VT220	Device subtype (VT220 in this example).
IOPAR	("auv":0:2048)	Any other OPEN parameters.
MSYS	M/WNT	Type of system (such as UNIX®, Windows).
POP	0	If not zero, specifies that no device was selected. That is, the user entered STOP in response to Device: prompt.
RMSDF	RW	Read/Write permissions.

15.1.5 OPEN Parameters

By default, the **OPEN** command uses the specifications for the device defined in the ^%IS global. You can override these settings by specifying other settings when you use ^%IS.

15.1.6 Issue a USE Command

After running ^%IS, the application must issue a **USE** command to the device opened by ^%IS. You can use the variable **IO**, as long as you understand that its value changes every time you call ^%IS. Then, subsequent InterSystems IRIS I/O commands, such as **READ** and **WRITE**, refer to that device.

15.1.7 Issue a CLOSE Command

The user or application developer must close devices opened with the ^%IS utility.

15.2 ^%IS Mnemonics

^%IS has several features to simplify its use. For example, if you want to send I/O to your own terminal, simply press **Enter** at the “Device” prompt. You can also use built-in default mnemonics or new mnemonics you define yourself.

15.2.1 Device Mnemonics

It is useful to have mnemonics for the various devices and, in some cases, to have more than one mnemonic for a single device. Multiple mnemonics allow you to specify different device characteristics for the device and vary characteristics according to the manner in which the device is used. For example, a terminal that is normally used for data entry, and thus has the characteristics of a terminal, may have an auxiliary printer attached. By assigning a different mnemonic that opens the same device with different characteristics, you can treat the terminal/printer combination as a printer when you want hard copy.

You can configure device mnemonics and characteristics using the Management Portal. To learn how to define and activate mnemonic spaces, see the section [Defining Default Mnemonic Spaces](#).

15.2.2 Default Mnemonics

The ^%IS global is initialized at installation with several default mnemonics. For instance, there are two default mnemonics, SPOOL and 2, for the InterSystems IRIS spooler. Simply type “2” or “SPOOL” to send output to the InterSystems IRIS spooler.

If you are logged in on an RT:, LT:, or VT: type device, and your terminal is the current device, ^%IS will accept 0, “”, or the value of *IO* in response to the “Device” prompt. It will use the appropriate template (RT0:, LT0: or VT0:) for your terminal type to generate the information for your terminal.

15.2.3 Alternate Devices

If users enter an “A” at the Device prompt, output goes to the alternate device defined for the current device. Usually, users expect the alternate device to be a printer. Instead of defining a separate alternate device for each device in the system, you can create a device, pointing to a printer, with the mnemonic “A”. Then, when users enter “A” at the ^%IS “Device” prompt, output goes to that device.

15.2.4 CURRENT^%IS Entry Point

CURRENT is an internal entry point within the ^%IS utility that you can use to obtain the device parameters of the current device. This call to ^%IS returns the values of different variables, so you can keep one set of parameters for your principal device and a different set for a device with different characteristics. Ordinarily, you make a call to this internal entry point when you log in, to allow the application access to the device characteristics of the principal device. **CURRENT^%IS** returns the values of the variables listed in the table below:

Table 15–2: CURRENT Return Values

Variable	Example	Description
FF	3	WRITE @FF should be used for form feed on this device
BS	*8	WRITE @BS should be used to backspace
RM	80	Right margin
SL	24	Screen/page length
SUB	C-VT100	Device subtype
XY	(see Example below)	Set \$X to DX and \$Y to DY to perform direct cursor positioning

15.2.5 Example

After calling **CURRENT^%IS**, set **\$X** and **\$Y** to **DX** and **DY** to position the cursor.

ObjectScript

```
DO CURRENT^%IS
WRITE *27,*61,*DY+32,*DX+32
SET $X=DX,$Y=DY
```

15.2.6 IN^%IS Entry Point

IN is an internal entry point within **^%IS** that can be called by routines that only plan to do input from the device. This entry point can be used to ensure that you do not select an output-only device such as a printer.

```
%SYS> Do IN^%IS

Device: 3
Right margin: 132= <RETURN>
[you can't read from this device]
Device: <RETURN>
Right margin: 80= <RETURN>
%SYS>
```

15.2.7 OUT^%IS Entry Point

OUT is an internal entry point within **^%IS** that can be called by routines that only plan to do output to the device.

15.2.8 Spooling

InterSystems IRIS spooling is independent of the spooling performed by your operating system. Spooling in InterSystems IRIS is a technique that lets you automatically save the output of a program in a global instead of printing it immediately. You can print the output later by sending the contents of the global to the printer.

The mnemonic **SPOOL** is a default mnemonic. To specify spooling, enter “**SPOOL**” in response to the Device prompt. The system then asks for a spool file name and description. This is a named used in the **^SPOOL** global—not a separate file name at the operating system level.

If any existing file names start with or match the name you specify, they are displayed, and you are asked to choose one. If you select none of the existing files, the system allows you to create a new file with the specified name and description as shown in the following example:

```
Device: SPOOL
Name:TEST
1. 1 TEST 02 Nov 1999 10:17 am First test
2. 2 TEST 02 Nov 1999 10:18 am Second Test
Select one: <Return> not found
Create new document 'TEST'? Yes => yes
Description: Third Test
```

If you reselect an existing document because you would like to continue adding to an existing file, the system gives you the following options:

1. Add to the very end of the file;
2. Restart at the top of the last page, in which case the lines that will be deleted are displayed on the screen;
3. Restart at page 1 (the beginning).

You can pass the variables listed in the table below to ^%IS when you call it for spooling.

Table 15–3: Spool Variables You Can Pass to ^%IS

Variable	Function
IODOC	Document name (when this variable exists and is not a null string all questions are suppressed, and a new document with this name is automatically created).
IODES	Free text description.
IOPGM	Name of a routine that should be called at print time to allow the user to set up printer for the proper forms alignment.

15.2.9 Further Features of ^%IS

^%IS can also be used to perform the following tasks:

- Right margin suppressing—It is possible to set up a terminal line so that whenever that device is selected, the Right margin question is suppressed; the default value is automatically assumed.
- Automatic device selection—If the variable *IOP* exists when the ^%IS utility is called, the utility automatically tries to open that device rather than ask for a device. If ^%IS is unsuccessful, it sets the variable *POP* to 1.
- Preconfigured terminals—Using the Management Portal, you can configure a device that does not request any device information from the user.

15.3 Structure of ^%IS Global

The ^%IS global is stored in the %SYS namespace. It contains two subscripts. The first subscript is the mnemonic name configured for the device in the Management Portal. Select **System Administration, Configuration, Device Settings, IO Settings** to display the default mnemonic for different device types. The second subscript can be 0 or 1.

15.3.1 Contents of Node 0

Node 0 contains the Device panel Location value:

```
^%IS(mnemonic,0) = Location
```

15.3.2 Contents of Node 1

Node 1 contains the other Device panel field values separated by a caret (^):

```
^%IS(mnemonic,1) = Device #^Type^Subtype^Prompt code^not used  
^Other Open parameters^Alternate device
```

In this example, the device with the mnemonic name 2 (which is a default name for the InterSystems IRIS spooler) has a device number of 2, device type of SPL (spool), device subtype of PK-DEC. The other values are not defined for a spool type device.

```
^%IS(2,1) = 2^SPL^PK-DEC^^^^^
```

16

Device Special Variables

Some I/O commands affect the value of certain system variables. This section defines these variables and tells why you might want to use them. These variables are changed only when an I/O command is issued to the current device. These device special variables are summarized in the table below:

Table 16–1: Device Special Variables

Variable	Purpose
\$IO	Contains the device ID of the current device, to which all output operations are directed. InterSystems IRIS sets the value of \$IO to the principal output device at login, and only the USE and CLOSE commands, a BREAK command, or a return to programmer mode can change this value.
\$X	Contains a running total of printable characters written since the last carriage return on the current device. This number ranges from 0 to the width of the device.
\$Y	Contains a running total of line feeds written since the last form feed on the current device. This number ranges from 0 to the length of the device.
\$ZA	Contains READ status information after a READ command to a terminal device.
\$ZB	Contains the character sequence or event ended the last READ operation on the current device.
\$ZMODE	Contains the parameters you used with the OPEN or USE command for the current device.

\$X and **\$Y** are useful in formatting printed output. For more information on them, see [Terminal I/O](#).

